

CDO User's Guide

Climate Data Operators
Version 1.2.1
November 2008

Uwe Schulzweida, Luis Kornblueh – *MPI for Meteorology*
Ralf Quast – *Brockmann Consult*

Contents

1. Introduction	6
1.1. Building from sources	6
1.1.1. Compilation	7
1.1.2. Installation	7
1.2. Usage	7
1.2.1. Options	8
1.2.2. Operators	8
1.2.3. Combining operators	8
1.2.4. Operator parameter	9
1.3. Grid description	9
1.3.1. Predefined grids	9
1.3.2. Grids from data files	10
1.3.3. SCRIP grids	10
1.3.4. PINGO grids	11
1.3.5. CDO grids	11
1.4. Z-axis description	12
1.5. Time axis	13
1.5.1. Absolute time	13
1.5.2. Relative time	13
1.5.3. Conversion of the time	13
1.6. Parameter table	14
1.7. Missing values	14
1.7.1. Mean and average	15
2. Reference manual	16
2.1. Information	17
2.1.1. INFO - Information and simple statistics	18
2.1.2. SINFO - Short information	19
2.1.3. DIFF - Compare two datasets field by field	20
2.1.4. NINFO - Print the number of parameters, levels or times	21
2.1.5. SHOWINFO - Show variables, levels or times	22
2.1.6. FILEDES - Dataset description	23
2.2. File operations	24
2.2.1. COPY - Copy datasets	25
2.2.2. REPLACE - Replace variables	25
2.2.3. MERGE - Merge datasets	26
2.2.4. SPLIT - Split a dataset	27
2.2.5. SPLITTIME - Split time steps of a dataset	28
2.2.6. SPLITSEL - Split selected time steps	29
2.3. Selection	30
2.3.1. SELECT - Select fields	31
2.3.2. SELTIME - Select time steps	33
2.3.3. SELBOX - Select a box of a field	35
2.4. Conditional selection	36
2.4.1. COND - Conditional select one field	37
2.4.2. COND2 - Conditional select two fields	37
2.4.3. CONDC - Conditional select a constant	38
2.5. Comparison	39
2.5.1. COMP - Comparison of two fields	40

2.5.2.	COMPC - Comparison of a field with a constant	41
2.6.	Modification	42
2.6.1.	SET - Set field info	43
2.6.2.	SETTIME - Set time	44
2.6.3.	CHANGE - Change field header	46
2.6.4.	SETGRID - Set grid type	47
2.6.5.	SETZAXIS - Set z-axis type	47
2.6.6.	SETGATT - Set global attribute	48
2.6.7.	INVERT - Invert latitudes	49
2.6.8.	INVERTLEV - Invert levels	49
2.6.9.	MASKREGION - Mask regions	50
2.6.10.	MASKBOX - Mask a box	51
2.6.11.	SETBOX - Set a box to constant	52
2.6.12.	ENLARGE - Enlarge fields	53
2.6.13.	SETMISS - Set missing value	54
2.7.	Arithmetic	55
2.7.1.	EXPR - Evaluate expressions	56
2.7.2.	MATH - Mathematical functions	57
2.7.3.	ARITHC - Arithmetic with a constant	58
2.7.4.	ARITH - Arithmetic on two datasets	59
2.7.5.	MONARITH - Monthly arithmetic	60
2.7.6.	YMONARITH - Multi-year monthly arithmetic	61
2.7.7.	ARITHDAYS - Arithmetic with days	62
2.8.	Statistical values	63
2.8.1.	ENSSTAT - Statistical values over an ensemble	67
2.8.2.	FLDSTAT - Statistical values over a field	69
2.8.3.	ZONSTAT - Zonal statistical values	71
2.8.4.	MERSTAT - Meridional statistical values	73
2.8.5.	VERTSTAT - Vertical statistical values	75
2.8.6.	TIMSELSTAT - Time range statistical values	76
2.8.7.	TIMSELPCTL - Time range percentile values	77
2.8.8.	RUNSTAT - Running statistical values	78
2.8.9.	RUNPCTL - Running percentile values	79
2.8.10.	TIMSTAT - Statistical values over all time steps	80
2.8.11.	TIMPCTL - Percentile values over all time steps	81
2.8.12.	HOURLSTAT - Hourly statistical values	82
2.8.13.	HOURLPCTL - Hourly percentile values	83
2.8.14.	DAYSTAT - Daily statistical values	84
2.8.15.	DAYPCTL - Daily percentile values	85
2.8.16.	MONSTAT - Monthly statistical values	86
2.8.17.	MONPCTL - Monthly percentile values	87
2.8.18.	YEARSTAT - Yearly statistical values	88
2.8.19.	YEARPCTL - Yearly percentile values	89
2.8.20.	SEASSTAT - Seasonal statistical values	90
2.8.21.	SEASPCTL - Seasonal percentile values	91
2.8.22.	YHOURLSTAT - Multi-year hourly statistical values	92
2.8.23.	YDAYSTAT - Multi-year daily statistical values	93
2.8.24.	YDAYPCTL - Multi-year daily percentile values	94
2.8.25.	YMONSTAT - Multi-year monthly statistical values	95
2.8.26.	YMONPCTL - Multi-year monthly percentile values	96
2.8.27.	YSEASSTAT - Multi-year seasonal statistical values	97
2.8.28.	YSEASPCTL - Multi-year seasonal percentile values	98
2.8.29.	YDRUNSTAT - Multi-year daily running statistical values	99
2.8.30.	YDRUNPCTL - Multi-year daily running percentile values	101
2.9.	Regression	102
2.9.1.	REGRES - Regression	103
2.9.2.	DETREND - Detrend time series	103
2.9.3.	TREND - Trend of time series	104

2.9.4. SUBTREND - Subtract a trend	104
2.10. Interpolation	105
2.10.1. REMAPGRID - SCRIP grid interpolation	106
2.10.2. GENWEIGHTS - Generate SCRIP grid interpolation weights	107
2.10.3. REMAP - SCRIP grid remapping	108
2.10.4. INTGRID - Grid interpolation	109
2.10.5. REMAPETA - Remap vertical hybrid level	110
2.10.6. INTVERT - Vertical interpolation	111
2.10.7. INTLEVEL - Linear level interpolation	112
2.10.8. INTTIME - Time interpolation	113
2.10.9. INTYEAR - Year interpolation	114
2.11. Transformation	115
2.11.1. SPECTRAL - Spectral transformation	116
2.11.2. WIND - Wind transformation	117
2.12. Formatted I/O	118
2.12.1. INPUT - Formatted input	119
2.12.2. OUTPUT - Formatted output	120
2.13. Miscellaneous	121
2.13.1. GRIDCELL - Grid cell quantities	122
2.13.2. GRADSDS - GrADS data descriptor file	123
2.13.3. SMOOTH9 - 9 point smoothing	124
2.13.4. SETRANGE - Set range to constant	124
2.13.5. TIMSORT - Timsort	125
2.13.6. VARGEN - Generate a field	125
2.13.7. ROTUV - Rotation	126
2.13.8. MASTRFU - Mass stream function	126
2.13.9. HISTOGRAM - Histogram	127
2.13.10.WCT - Windchill temperature	128
2.13.11.FDNS - Frost days where no snow index per time period	128
2.13.12.STRWIN - Strong wind days index per time period	128
2.13.13.STRBRE - Strong breeze days index per time period	129
2.13.14.STRGAL - Strong gale days index per time period	129
2.13.15.HURR - Hurricane days index per time period	129
2.13.16.IMPORTAMSR - Import AMSR binary files	130
2.13.17.IMPORTCMSAF - Import CM-SAF files	130
2.14. Climate indices	131
2.14.1. ECACDD - Consecutive dry days index per time period	133
2.14.2. ECACFD - Consecutive frost days index per time period	133
2.14.3. ECACSU - Consecutive summer days index per time period	134
2.14.4. ECACWD - Consecutive wet days index per time period	134
2.14.5. ECACWDI - Cold wave duration index wrt mean of reference period	135
2.14.6. ECACWFI - Cold-spell days index wrt 10th percentile of reference period	135
2.14.7. ECAETR - Intra-period extreme temperature range	136
2.14.8. ECAFD - Frost days index per time period	136
2.14.9. ECAGSL - Growing season length index	137
2.14.10.ECAHD - Heating degree days per time period	138
2.14.11.ECAHWDI - Heat wave duration index wrt mean of reference period	138
2.14.12.ECAHWFI - Warm spell days index wrt 90th percentile of reference period	139
2.14.13.ECAID - Ice days index per time period	139
2.14.14.ECAR10MM - Heavy precipitation days index per time period	140
2.14.15.ECAR20MM - Very heavy precipitation days index per time period	140
2.14.16.ECAR75P - Moderate wet days wrt 75th percentile of reference period	141
2.14.17.ECAR75PTOT - Precipitation percent due to R75p days	141
2.14.18.ECAR90P - Wet days wrt 90th percentile of reference period	142
2.14.19.ECAR90PTOT - Precipitation percent due to R90p days	142
2.14.20.ECAR95P - Very wet days wrt 95th percentile of reference period	143
2.14.21.ECAR95PTOT - Precipitation percent due to R95p days	143
2.14.22.ECAR99P - Extremely wet days wrt 99th percentile of reference period	144

2.14.23.ECAR99PTOT - Precipitation percent due to R99p days	144
2.14.24.ECARR1 - Wet days index per time period	145
2.14.25.ECARX1DAY - Highest one day precipitation amount per time period	145
2.14.26.ECARX5DAY - Highest five-day precipitation amount per time period	146
2.14.27.ECASDII - Simple daily intensity index per time period	146
2.14.28.ECASU - Summer days index per time period	146
2.14.29.ECATG10P - Cold days percent wrt 10th percentile of reference period	148
2.14.30.ECATG90P - Warm days percent wrt 90th percentile of reference period	148
2.14.31.ECATN10P - Cold nights percent wrt 10th percentile of reference period	149
2.14.32.ECATN90P - Warm nights percent wrt 90th percentile of reference period	149
2.14.33.ECATR - Tropical nights index per time period	150
2.14.34.ECATX10P - Very cold days percent wrt 10th percentile of reference period	150
2.14.35.ECATX90P - Very warm days percent wrt 90th percentile of reference period	151
A. Hints for PINGO user	153
B. Grid description examples	154
B.1. Example of a curvilinear grid description	154
B.2. Example description for unstructured grid cells	155
Operator index	156

1. Introduction

The Climate Data Operators (**CDO**) software are a collection of many operators for standard processing of climate and forecast model output. The operators include simple statistical and arithmetic functions, data selection and subsampling tools, and spatial interpolation. **CDO** was developed to have the same set of processing functions for [GRIB](#) and [netCDF](#) datasets in one package.

The Climate Data Interface (**CDI**) is used for the fast and file format independent access to [GRIB](#) and [netCDF](#) datasets. The local data formats SERVICE, EXTRA and IEG are also supported.

There are some limitations for [GRIB](#) and [netCDF](#) datasets. A [GRIB](#) dataset has to be consistent, similar to [netCDF](#). That means all time steps need to have the same variables, and within a time step each variable may occur only once. [NetCDF](#) datasets are supported only with 2-dimensional, 3-dimensional and 4-dimensional variables and the attributes should follow the [GDT](#), [COARDS](#) or [CF Conventions](#).

The user interface and some operators are similar to the [PINGO](#) package. There are also some operators with the same name as in [PINGO](#) but with a different meaning. [Appendix A](#) gives an overview of those operators.

The main **CDO** features are:

- More than 400 operators available
- Modular design and easily extendable with new operators
- Very simple UNIX command line interface
- A dataset can be processed by several operators, without storing the interim results in files
- Most operators handle datasets with missing values
- Fast processing of large datasets
- Support of many different grid types
- Tested on many UNIX/Linux systems, Cygwin, and MacOS-X

1.1. Building from sources

This section describes how to build **CDO** from the sources on a UNIX system. **CDO** uses the GNU configure and build system for compilation. The only requirement is a working ANSI C compiler.

First go to the [download](#) page (<http://www.mpimet.mpg.de/cdo>) to get the latest distribution, if you do not have it yet.

To take full advantage of **CDO** features the following additional libraries should be installed.

- Unidata [netCDF](#) library (<http://www.unidata.ucar.edu/packages/netcdf>) version 3 or higher.
This is needed to process [netCDF](#) files with **CDO**.
- HDF5 [gzip](#) library (http://hdf.ncsa.uiuc.edu/doc_resource/SZIP) version 2.1 or higher.
This is needed to process [gzip](#) compressed [GRIB](#) files with **CDO**.

1.1.1. Compilation

Compilation is done by performing the following steps:

1. Unpack the archive, if you haven't done that yet:

```
gunzip cdo-$VERSION.tar.gz    # uncompress the archive
tar xf cdo-$VERSION.tar       # unpack it
cd cdo-$VERSION
```

2. Run the configure script:

```
./configure
```

Or with [netCDF](#) support:

```
./configure --with-netcdf=<netCDF root directory>
```

To enable [gzip](#) support add:

```
--with-szlib=<SZLIB root directory>
```

For an overview of other configuration options use

```
./configure --help
```

3. Compile the program by running make:

```
make
```

The program should compile without problems and the binary (`cdo`) should be available in the `src` directory of the distribution.

1.1.2. Installation

After the compilation of the source code do a `make install`, possibly as root if the destination permissions require that.

```
make install
```

The binary is installed into the directory `<prefix>/bin`. `<prefix>` defaults to `/usr/local` but can be changed with the `--prefix` option of the configure script.

Alternatively, you can also copy the binary from the `src` directory manually to some `bin` directory in your search path.

1.2. Usage

This section describes how to use **CDO**. The syntax is:

```
cdo [ Options ] Operator1 [ -Operator2 [ -OperatorN ] ]
```

1.2.1. Options

All options have to be placed before the first operator. The following options are available for all operators:

- a Convert from a relative to an absolute time axis.
 -b <nbits> Set the number of bits for output precision. The valid precisions depend on the file format:

<format>	<nbits>
grb	1 - 32
nc, nc2, nc4, srv, ext, ieg	32/64

For **srv**, **ext** and **ieg** format an L or B can be added to set the byteorder to Little or Big endian.

- f <format> Set the output file format. The valid file formats are:

File format	<format>
GRIB version 1	grb
netCDF	nc
netCDF version 2 (64-bit)	nc2
netCDF-4 classic (HDF5)	nc4
SERVICE	srv
EXTRA	ext
IEG	ieg

- g <grid> Define the default grid description by name or from file (see chapter 1.3 on page 9). Available grid names are: **t<RES>grid**, **r<NX>x<NY>**, **gme<NI>**
 -h Help information for the operators.
 -m <missval> Set the default missing value (default: **-9e+33**).
 -R Convert GRIB data from reduced to regular grid.
 -r Convert from an absolute to a relative time axis.
 -s Silent mode.
 -t <partab> Set the default parameter table name or file (see chapter 1.6 on page 14). Predefined tables are: **echam4 echam5 mpiom1**
 -V Print the version number.
 -v Print extra details for some operators.
 -z *szip* Compress GRIB records with szip.
 zip Deflate compression of netCDF4 variables.

1.2.2. Operators

There are more than 400 operators available. A detailed description of all operators can be found in the [Reference Manual](#) section.

1.2.3. Combining operators

All operators with a fixed number of input streams and one output stream can pipe the result directly to an other operator. The operator must begin with "-", in order to combine it with others. This can improve the performance by:

- reducing unnecessary disk I/O
- parallel processing

Use

```
cdo sub -dayavg ifile2 -timavg ifile1 ofile
```


instead of

```
cdo timavg ifile1 tmp1
cdo dayavg ifile2 tmp2
cdo sub tmp2 tmp1 ofile
rm tmp1 tmp2
```

Combining of operators is implemented over POSIX Threads (pthread). Therefore this **CDO** feature is not available on operating systems without POSIX Threads support.

1.2.4. Operator parameter

Some operators need one or more parameter.

- **STRING**

Unquoted characters without blanks and tabs. The following command select the variables with the names **pressure** and **tsurf**:

```
cdo selvar,pressure,tsurf ifile ofile
```

- **FLOAT**

Floating point number in any representation. The following command sets the range between 0 and 273.15 of all fields to missing value:

```
cdo setrtomiss,0,273.15 ifile ofile
```

- **INTEGER**

A list of integers can be specified by *first/last[/inc]*. To select the days 5, 6, 7, 8 and 9 use:

```
cdo selday,5/9 ifile ofile
```

This is the same as:

```
cdo selday,5,6,7,8,9 ifile ofile
```

1.3. Grid description

In the following situations it is necessary to give a description of a horizontal grid:

- Changing the grid description (operator: [setgrid](#))
- Horizontal interpolation (operator: [interpolate](#), [remapXXX](#) and [genXXX](#))
- Generating variables (operator: [const](#), [random](#))

As now described, there are several possibilities to define a horizontal grid. Predefined grids are available for global regular, gaussian or icosahedral-hexagonal GME grids.

1.3.1. Predefined grids

The following pre-defined grid names are available: **r<NX>x<NY>**, **t<RES>grid** and **gme<NI>**

Global regular grid: $r\langle NX \rangle \times \langle NY \rangle$

$r\langle NX \rangle \times \langle NY \rangle$ defines a global regular grid. The number of the longitudes $\langle NX \rangle$ and the latitudes $\langle NY \rangle$ can be selected at will. The longitudes start at 0° with an increment of $(360/\langle NX \rangle)^\circ$. The latitudes go from south to north with an increment of $(180/\langle NY \rangle)^\circ$.

Global gaussian grid: $t\langle RES \rangle \text{grid}$

$t\langle RES \rangle \text{grid}$ defines a global gaussian grid. Each valid triangular resolution can be used for $\langle RES \rangle$. The longitudes start at 0° with an increment of $(360/nlon)^\circ$. The gaussian latitudes go from north to south.

Global icosahedral-hexagonal GME grid: $gme\langle NI \rangle$

$gme\langle NI \rangle$ defines a global icosahedral-hexagonal GME grid. NI is the number of intervals on a main triangle side.

1.3.2. Grids from data files

You can use the grid description from an other datafile. The format of the datafile and the grid of the data field must be supported by this program. Use the operator '[sinfo](#)' to get short informations about your variables and the grids. If there are more then one grid in the datafile the grid description of the first variable will be used.

1.3.3. SCRIP grids

SCRIP is a Spherical Coordinate Remapping and Interpolation Package. It uses a common grid description in netCDF. You can use it to describe curvilinear grids or unstructured grid cells. For more information about this format see [[SCRIP](#)]. That grid description format is only available if the program was compiled with netCDF support.

SCRIP grid description example of a curvilinear [MPIOM](#) GROB3 grid (only the netCDF header):

```
netcdf grob3s {
  dimensions:
    grid_size = 12120 ;
    grid_xsize = 120 ;
    grid_ysize = 101 ;
    grid_corners = 4 ;
    grid_rank = 2 ;
  variables:
    int grid_dims(grid_rank) ;
    float grid_center_lat(grid_ysize, grid_xsize) ;
      grid_center_lat:units = "degrees" ;
      grid_center_lat:bounds = "grid_corner_lat" ;
    float grid_center_lon(grid_ysize, grid_xsize) ;
      grid_center_lon:units = "degrees" ;
      grid_center_lon:bounds = "grid_corner_lon" ;
    int grid_imask(grid_ysize, grid_xsize) ;
      grid_imask:units = "unitless" ;
      grid_imask:coordinates = "grid_center_lon grid_center_lat" ;
    float grid_corner_lat(grid_ysize, grid_xsize, grid_corners) ;
      grid_corner_lat:units = "degrees" ;
    float grid_corner_lon(grid_ysize, grid_xsize, grid_corners) ;
      grid_corner_lon:units = "degrees" ;

  // global attributes:
    :title = "grob3s" ;
}
```

1.3.4. PINGO grids

PINGO uses a very simple grid description in ASCII format to describe regular longitude/latitude or global gaussian grids. All PINGO grid description files are supported by **CDO**. For more information about this format see [\[PINGO\]](#).

PINGO grid description example of a T21 gaussian grid:

```
Grid Description File
(Comments start at non digit characters and end at end of line)
First part: The dimensions.
64 32 = Number of longitudes and latitudes
Second part: The listed longitudes.
2 means equidistant longitudes
0.000000 5.625000 = Most western and second most western longitude
Third part: The listed latitudes.
32 means all 32 latitudes are given in the following list:
85.761 80.269 74.745 69.213 63.679 58.143 52.607 47.070
41.532 35.995 30.458 24.920 19.382 13.844 8.307 2.769
-2.769 -8.307 -13.844 -19.382 -24.920 -30.458 -35.995 -41.532
-47.070 -52.607 -58.143 -63.679 -69.213 -74.745 -80.269 -85.761
```

1.3.5. CDO grids

All supported grids can also be described with the **CDO** grid description. The following keywords can be used to describe a grid:

Keyword	Datatype	Description
gridtype	STRING	type of the grid (gaussian, lonlat, curvilinear, cell)
gridsize	INTEGER	size of the grid
xsize	INTEGER	size in x direction (number of longitudes)
ysize	INTEGER	size in y direction (number of latitudes)
xvals	FLOAT ARRAY	x values of the grid
yvals	FLOAT ARRAY	y values of the grid
xnpole	FLOAT	x value of the north pole (rotated grid)
ynpole	FLOAT	y value of the north pole (rotated grid)
nvertex	INTEGER	number of the vertices for all grid cells
xbounds	FLOAT ARRAY	x bounds of each gridbox
ybounds	FLOAT ARRAY	y bounds of each gridbox
xfirst, xinc	FLOAT, FLOAT	macros to define xvals with a constant increment
yfirst, yinc	FLOAT, FLOAT	macros to define yvals with a constant increment

Which keywords are necessary depends on the gridtype. The following table gives an overview of the default values or the size with respect to the different grid types.

gridtype	lonlat	gaussian	curvilinear	cell
gridsize	xsize*ysize	xsize*ysize	xsize*ysize	ncell
xsize	nlon	nlon	nlon	gridsize
ysize	nlat	nlat	nlat	gridsize
xvals	xsize	xsize	gridsize	gridsize
yvals	ysize	ysize	gridsize	gridsize
xnpole	0			
ynpole	90			
nvertex	2	2	4	nv
xbounds	2*xsize	2*xsize	4*gridsize	nv*gridsize
ybounds	2*ysize	2*ysize	4*gridsize	nv*gridsize

The keywords `nvertex`, `xbounds` and `ybounds` are optional if area weights are not needed.

CDO grid description example of a T21 gaussian grid:

```
gridtype = gaussian
xsize    = 64
ysize    = 32
xfirst   = 0
xinc     = 5.625
yvals    = 85.76  80.27  74.75  69.21  63.68  58.14  52.61  47.07
           41.53  36.00  30.46  24.92  19.38  13.84  8.31   2.77
           -2.77 -8.31 -13.84 -19.38 -24.92 -30.46 -36.00 -41.53
           -47.07 -52.61 -58.14 -63.68 -69.21 -74.75 -80.27 -85.76
```

CDO grid description example of a global regular grid with 60x30 points:

```
gridtype = lonlat
xsize    = 60
ysize    = 30
xfirst   = -177
xinc     = 6
yfirst   = -87
yinc     = 6
```

For a lon/lat grid with a rotated pole, the north pole must be defined. As far as you define the keywords `xnpole`/`ynpole` all coordinate values are for the rotated system.

CDO grid description example of a regional rotated lon/lat grid:

```
gridtype = lonlat
xsize    = 81
ysize    = 91
xfirst   = -19.5
xinc     = 0.5
yfirst   = -25.0
yinc     = 0.5
xnpole   = -170
ynpole   = 32.5
```

Example **CDO** descriptions of a curvilinear and an unstructured grid can be found in [Appendix B](#).

1.4. Z-axis description

Sometimes it is necessary to change the description of a z-axis. This can be done with the operator `setzaxis`. This operator needs an ASCII formatted file with the description of the z-axis. The following keywords can be used to describe a z-axis:

Keyword	Datatype	Description
zaxistype	STRING	type of the z-axis
size	INTEGER	number of levels
levels	FLOAT ARRAY	values of the levels
lbounds	FLOAT ARRAY	lower level bounds
ubounds	FLOAT ARRAY	upper level bounds
vctsize	INTEGER	number of vertical coordinate parameters
vct	FLOAT ARRAY	vertical coordinate table

The keywords **lbounds** and **ubounds** are optional. **vctsize** and **vct** are only necessary to define hybrid model levels.

Available z-axis types:

Z-axis type	Description	Units
surface	Surface	
pressure	Pressure level	pascal
hybrid	Hybrid model level	
height	Height above ground	meter
depth_below_sea	Depth below sea level	meter
depth_below_land	Depth below land surface	centimeter
isentropic	Isentropic (theta) level	kelvin

Z-axis description example for pressure levels 100, 200, 500, 850 and 1000 hPa:

```
zaxistype = pressure
size      = 5
levels    = 10000 20000 50000 85000 100000
```

Z-axis description example for ECHAM5 L19 hybrid model levels:

```
zaxistype = hybrid
size      = 19
levels    = 1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19
vctsize   = 40
vct       = 0 2000 4000 6046.10938 8267.92578 10609.5117 12851.1016 14698.5
            15861.125 16116.2383 15356.9258 13621.4609 11101.5625 8127.14453
            5125.14062 2549.96875 783.195068 0 0 0
            0 0 0 0.000338993268 0.00335718691 0.0130700432 0.0340771675
            0.0706498027 0.12591666 0.201195419 0.295519829 0.405408859
            0.524931908 0.646107674 0.759697914 0.856437683 0.928747177
            0.972985268 0.992281914 1
```

1.5. Time axis

A time axis describes the time for every timestep. Two time axis types are available: absolute time and relative time axis. **CDO** tries to maintain the actual type of the time axis for all operators. Some time range statistic operators create an absolute time axis (e.g. `timsel<STAT>`, `run<STAT>`, `seas<STAT>`, ...).

1.5.1. Absolute time

An absolute time axis has the current time to each time step. It can be used without knowledge of the calendar. This is preferably used by climate models. In netCDF files the absolute time axis is represented by the unit of the time: `"day as %Y%m%d.%f"`.

1.5.2. Relative time

A relative time is the time relative to a fixed reference time. The current time results from the reference time and the elapsed interval. The result depends on the calendar used. **CDO** supports the standard Gregorian, 360 days, 365 days and 366 days calendars. The relative time axis is preferably used by weather forecast models. In netCDF files the relative time axis is represented by the unit of the time: `"time-units since reference-time"`, e.g. `"days since 1989-6-15 12:00"`.

1.5.3. Conversion of the time

Some programs which work with netCDF data can only process relative time axes. Therefore it may be necessary to convert from an absolute into a relative time axis. This conversion can be done for each operator with the **CDO** option `'-r'`. To convert a relative into an absolute time axis use the **CDO** option `'-a'`.

1.6. Parameter table

A parameter table is an ASCII formatted file to convert code numbers to variable names. Each variable has one line with its code number, name and a description with optional units in a blank separated list. It can only be used for GRIB, SERVICE, EXTRA and IEG formatted files. The **CDO** option '`-t <partab>`' sets the default parameter table for all input files. Use the operator '`setpartab`' to set the parameter table for a specific file.

Example of a **CDO** parameter table:

134	aps	surface pressure [Pa]
141	sn	snow depth [m]
147	ahfl	latent heat flux [W/m**2]
172	slm	land sea mask
175	albedo	surface albedo
211	siced	ice depth [m]

1.7. Missing values

Most operators can handle missing values. The default missing value for GRIB, SERVICE, EXTRA and IEG files is $-9e + 33$. The **CDO** option '`-m <missval>`' overwrites the default missing value. In netCDF files the variable attribute '`_FillValue`' is used as a missing value. The operator '`setmissval`' can be used to set a new missing value.

The **CDO** use of the missing value is shown in the following tables, where one table is printed for each operation. The operations are applied to arbitrary numbers a , b , the special case 0, and the missing value *miss*. For example the table named "addition" shows that the sum of an arbitrary number a and the missing value is the missing value, and the table named "multiplication" shows that 0 multiplied by missing value results in 0.

addition	b	miss	
a	$a + b$	miss	
miss	miss	miss	
subtraction	b	miss	
a	$a - b$	miss	
miss	miss	miss	
multiplication	b	0	miss
a	$a * b$	0	miss
0	0	0	0
miss	miss	0	miss
division	b	0	miss
a	a/b	miss	miss
0	0	miss	miss
miss	miss	miss	miss
maximum	b	miss	
a	$\max(a, b)$	a	
miss	b	miss	
minimum	b	miss	
a	$\min(a, b)$	a	
miss	b	miss	

The handling of missing values by the operations "minimum" and "maximum" may be surprising, but the

definition given here is more consistent with that expected in practice. Mathematical functions (e.g. *log*, *sqrt*, etc.) return the missing value if an argument is the missing value or an argument is out of range.

All statistical functions ignore missing values, treating them as not belonging to the sample, with the side-effect of a reduced sample size.

1.7.1. Mean and average

An artificial distinction is made between the notions mean and average. The mean is regarded as a statistical function, whereas the average is found simply by adding the sample members and dividing the result by the sample size. For example, the mean of 1, 2, *miss* and 3 is $(1 + 2 + 3)/3 = 2$, whereas the average is $(1 + 2 + \textit{miss} + 3)/4 = \textit{miss}/4 = \textit{miss}$. If there are no missing values in the sample, the average and mean are identical.

2. Reference manual

This section gives a description of all operators. Related operators are grouped to modules. For easier description all single input files are named `ifile` or `ifile1`, `ifile2`, etc., and an unlimited number of input files are named `ifiles`. All output files are named `ofile` or `ofile1`, `ofile2`, etc. Further the following notion is introduced:

$i(t)$	Timestep t of <code>ifile</code>
$i(t, x)$	Element number x of the field at timestep t of <code>ifile</code>
$o(t)$	Timestep t of <code>ofile</code>
$o(t, x)$	Element number x of the field at timestep t of <code>ofile</code>

2.1. Information

This section contains modules to print information about datasets. All operators print their results to standard output.

Here is a short overview of all operators in this section:

info	Dataset information listed by code number
infov	Dataset information listed by variable name
map	Dataset information and simple map
sinfo	Short dataset information listed by code number
sinfov	Short dataset information listed by variable name
diff	Compare two datasets listed by code number
diffv	Compare two datasets listed by variable name
npar	Number of parameters
nlevel	Number of levels
nyear	Number of years
nmon	Number of months
ndate	Number of dates
ntime	Number of time steps
showformat	Show file format
showcode	Show code numbers
showname	Show variable names
showstdname	Show standard names
showlevel	Show levels
showltype	Show GRIB level types
showyear	Show years
showmon	Show months
showdate	Show dates
showtime	Show time steps
pardes	Parameter description
griddes	Grid description
zaxisdes	Z-axis description
vct	Vertical coordinate table

2.1.1. INFO - Information and simple statistics

Synopsis

```
<operator> ifiles
```

Description

This module writes information about the structure and contents of all input datasets to standard output. The information displayed depends on the chosen operator.

Operators

- info** Dataset information listed by code number
Prints information and simple statistics for each field of all input datasets. For each field the operator prints one line with the following elements:
- Date and Time
 - Code number and Level
 - Size of the grid and number of Missing values
 - Minimum, Mean and Maximum
- The mean value is computed without the use of area weights!
- infov** Dataset information listed by variable name
The same as operator [info](#) but using the name instead of the code number to identify the variables.
- map** Dataset information and simple map
Prints information, simple statistics and a map for each field of all input datasets. The map will be printed only for fields on a rectangular grid.

Example

To print information and simple statistics for each field of a dataset use:

```
cdo info ifile
```

This is an example result of a dataset with one 2D variable over 12 time steps:

-1 :	Date	Time	Code	Level	Size	Miss :	Minimum	Mean	Maximum
1 :	1987-01-31	12:00	139	0	2048	1361 :	232.77	266.65	305.31
2 :	1987-02-28	12:00	139	0	2048	1361 :	233.64	267.11	307.15
3 :	1987-03-31	12:00	139	0	2048	1361 :	225.31	267.52	307.67
4 :	1987-04-30	12:00	139	0	2048	1361 :	215.68	268.65	310.47
5 :	1987-05-31	12:00	139	0	2048	1361 :	215.78	271.53	312.49
6 :	1987-06-30	12:00	139	0	2048	1361 :	212.89	272.80	314.18
7 :	1987-07-31	12:00	139	0	2048	1361 :	209.52	274.29	316.34
8 :	1987-08-31	12:00	139	0	2048	1361 :	210.48	274.41	315.83
9 :	1987-09-30	12:00	139	0	2048	1361 :	210.48	272.37	312.86
10 :	1987-10-31	12:00	139	0	2048	1361 :	219.46	270.53	309.51
11 :	1987-11-30	12:00	139	0	2048	1361 :	230.98	269.85	308.61
12 :	1987-12-31	12:00	139	0	2048	1361 :	241.25	269.94	309.27

2.1.2. SINFO - Short information

Synopsis

```
<operator> ifiles
```

Description

This module writes information about the structure of all input datasets to standard output. The information displayed depends on the chosen operator.

Operators

- sinfo** Short dataset information listed by code number
Prints short information of a dataset. The information is divided into 4 sections. Section 1 prints one line per variable with the following information:
- institute and source
 - parameter table and code number
 - horizontal grid size and number
 - number of vertical levels and z-axis number
- Section 2 and 3 gives a short overview of all horizontal and vertical grids. And the last section contains short information of the time axis.
- sinfov** Short dataset information listed by variable name
The same as operator [sinfo](#) but using the name instead of the code number and parameter table to identify the variables.

Example

To print short information of a dataset use:

```
cdo sinfo ifile
```

This is the result of an ECHAM5 dataset with 3 variables over 12 time steps:

```
-1 : Institut Source Table Code Time Typ Grid Size Num Levels Num
 1 : MPIMET ECHAM5.3 128 129 constant F32 2048 1 1 1
 2 : MPIMET ECHAM5.3 128 130 variable F32 2048 1 4 2
 3 : MPIMET ECHAM5.3 128 139 variable F32 2048 1 1 1
Horizontal grids :
 1 : gaussian > size : dim = 2048 nlon = 64 nlat = 32
      longitude : first = 0 last = 354.375 inc = 5.625
      latitude : first = 85.7605871 last = -85.7605871
Vertical grids :
 1 : surface : 0
 2 : pressure Pa : 92500 85000 50000 20000
Time axis : 12 steps
YYYY-MM-DD hh:mm YYYY-MM-DD hh:mm YYYY-MM-DD hh:mm YYYY-MM-DD hh:mm
1987-01-31 12:00 1987-02-28 12:00 1987-03-31 12:00 1987-04-30 12:00
1987-05-31 12:00 1987-06-30 12:00 1987-07-31 12:00 1987-08-31 12:00
1987-09-30 12:00 1987-10-31 12:00 1987-11-30 12:00 1987-12-31 12:00
```

2.1.3. DIFF - Compare two datasets field by field

Synopsis

```
<operator> ifile1 ifile2
```

Description

Compares the contents of two datasets field by field. The input datasets need to have the same structure and its fields need to have the same header information and dimensions.

Operators

diff Compare two datasets listed by code number
Provides statistics on differences between two datasets. For each pair of fields the operator prints one line with the following information:

- Date and Time
- Code number and Level
- Size of the grid and number of Missing values
- Occurrence of coefficient pairs with different signs (S)
- Occurrence of zero values (Z)
- Maxima of absolute difference of coefficient pairs
- Maxima of relative difference of non-zero coefficient pairs with equal signs

$$Absdiff(t, x) = |i_1(t, x) - i_2(t, x)|$$

$$Reldiff(t, x) = \frac{|i_1(t, x) - i_2(t, x)|}{\max(|i_1(t, x)|, |i_2(t, x)|)}$$

diffv Compare two datasets listed by variable name
The same as operator **diff**. Using the name instead of the code number to identify the variable.

Example

To print the difference for each field of two datasets use:

```
cdo diff ifile1 ifile2
```

This is an example result of two datasets with one 2D variable over 12 time steps:

	Date	Time	Code	Level	Size	Miss	: S Z	Max_Absdiff	Max_Reldiff
1 :	1987-01-31	12:00	139	0	2048	1361	: F F	0.00010681	4.1660e-07
2 :	1987-02-28	12:00	139	0	2048	1361	: F F	6.1035e-05	2.3742e-07
3 :	1987-03-31	12:00	139	0	2048	1361	: F F	7.6294e-05	3.3784e-07
4 :	1987-04-30	12:00	139	0	2048	1361	: F F	7.6294e-05	3.5117e-07
5 :	1987-05-31	12:00	139	0	2048	1361	: F F	0.00010681	4.0307e-07
6 :	1987-06-30	12:00	139	0	2048	1361	: F F	0.00010681	4.2670e-07
7 :	1987-07-31	12:00	139	0	2048	1361	: F F	9.1553e-05	3.5634e-07
8 :	1987-08-31	12:00	139	0	2048	1361	: F F	7.6294e-05	2.8849e-07
9 :	1987-09-30	12:00	139	0	2048	1361	: F F	7.6294e-05	3.6168e-07
10 :	1987-10-31	12:00	139	0	2048	1361	: F F	9.1553e-05	3.5001e-07
11 :	1987-11-30	12:00	139	0	2048	1361	: F F	6.1035e-05	2.3839e-07
12 :	1987-12-31	12:00	139	0	2048	1361	: F F	9.3553e-05	3.7624e-07

2.1.4. NINFO - Print the number of parameters, levels or times

Synopsis

`<operator> ifile`

Description

This module prints the number of variables, levels or times of the input dataset.

Operators

npar	Number of parameters Prints the number of parameters (variables).
nlevel	Number of levels Prints the number of levels for each variable.
nyear	Number of years Prints the number of different years.
nmon	Number of months Prints the number of different combinations of years and months.
ndate	Number of dates Prints the number of different dates.
ntime	Number of time steps Prints the number of time steps.

Example

To print the number of parameters (variables) in a dataset use:

```
cdo npar ifile
```

To print the number of months in a dataset use:

```
cdo nmon ifile
```

2.1.5. SHOWINFO - Show variables, levels or times

Synopsis

`<operator> ifile`

Description

This module prints the format, variables, levels or times of the input dataset.

Operators

showformat	Show file format Prints the file format of the input dataset.
showcode	Show code numbers Prints the code number of all variables.
showname	Show variable names Prints the name of all variables.
showstdname	Show standard names Prints the standard name of all variables.
showlevel	Show levels Prints all levels for each variable.
showltype	Show GRIB level types Prints the GRIB level type for all z-axes.
showyear	Show years Prints all years.
showmon	Show months Prints all months.
showdate	Show dates Prints all dates.
showtime	Show time steps Prints all time steps.

Example

To print the code number of all variables in a dataset use:

```
cdo showcode ifile
```

This is an example result of a dataset with three variables:

```
129 130 139
```

To print all months in a dataset use:

```
cdo showmon ifile
```

This is an examples result of a dataset with an annual cycle:

```
1 2 3 4 5 6 7 8 9 10 11 12
```

2.1.6. FILEDES - Dataset description

Synopsis

```
<operator> ifile
```

Description

This module prints the description of the parameters, the grids, the z-axis or the vertical coordinate table.

Operators

pardes	Parameter description Prints a table with a description of all variables. For each variable the operator prints one line listing the code, name, description and units.
griddes	Grid description Prints the description of all grids.
zaxisdes	Z-axis description Prints the description of all z-axes.
vct	Vertical coordinate table Prints the vertical coordinate table.

Example

Assume all variables of the dataset are on a T21 gaussian grid. To print the grid description of this dataset use:

```
cdo griddes ifile
```

Result:

```
gridtype : gaussian
gridsize : 2048
xname    : lon
xlongname : longitude
xunits   : degrees_east
yname    : lat
ylongname : latitude
yunits   : degrees_north
xsize    : 64
ysize    : 32
xfirst   : 0
xinc     : 5.625
yvals    : 85.76058 80.26877 74.74454 69.21297 63.67863 58.1429 52.6065
           47.06964 41.53246 35.99507 30.4575 24.91992 19.38223 13.84448
           8.306702 2.768903 -2.768903 -8.306702 -13.84448 -19.38223
           -24.91992 -30.4575 -35.99507 -41.53246 -47.06964 -52.6065
           -58.1429 -63.67863 -69.21297 -74.74454 -80.26877 -85.76058
```

2.2. File operations

This section contains modules to perform operations on files.

Here is a short overview of all operators in this section:

copy	Copy datasets
cat	Concatenate datasets
replace	Replace variables
merge	Merge datasets with different fields
mergetime	Merge datasets sorted by date and time
splitcode	Split code numbers
splitname	Split variable names
splitlevel	Split levels
splitgrid	Split grids
splitzaxis	Split z-axes
splithour	Split hours
splitday	Split days
splitmon	Split months
splitseas	Split seasons
splityear	Split years
splitsel	Split time selection

2.2.1. COPY - Copy datasets

Synopsis

```
<operator> ifiles ofile
```

Description

This module contains operators to copy or concatenate datasets. Each input dataset is required to have the same variables with complete time steps.

Operators

copy	Copy datasets Copies all input datasets to ofile .
cat	Concatenate datasets Concatenates all input datasets and appends the result to the end of ofile . If ofile does not exist it will be created.

Example

To change the format of a dataset to netCDF use:

```
cdo -f nc copy ifile ofile.nc
```

Add the option '-r' to create a relative time axis, as is required for proper recognition by GrADS or Ferret:

```
cdo -r -f nc copy ifile ofile.nc
```

To concatenate 3 datasets with different time steps of the same variables use:

```
cdo copy ifile1 ifile2 ifile3 ofile
```

If the output dataset already exists and you wish to extend it with more time steps use:

```
cdo cat ifile1 ifile2 ifile3 ofile
```

2.2.2. REPLACE - Replace variables

Synopsis

```
replace ifile1 ifile2 ofile
```

Description

Replaces all common variables of **ifile2** and **ifile1** with those of **ifile1** and write the result to **ofile**. Both input datasets need to have the same number of time steps.

Example

Assume the first input dataset **ifile1** has three variables with the names **geosp**, **t** and **tslm1** and the second input dataset **ifile2** has only the variable **tslm1**. To replace the variable **tslm1** in **ifile1** with **tslm1** from **ifile2** use:

```
cdo replace ifile1 ifile2 ofile
```

2.2.3. MERGE - Merge datasets

Synopsis

```
<operator> ifiles ofile
```

Description

This module reads datasets from several input files, merges them and writes the resulting dataset to `ofile`.

Operators

merge	Merge datasets with different fields Merges time series of different fields from several input datasets. The number of fields per time step written to <code>ofile</code> is the sum of the field numbers per time step in all input datasets. The time series on all input datasets are required to have different fields and the same number of time steps.
mergetime	Merge datasets sorted by date and time Merges all time steps of all input files sorted by date and time. After this operation every input time step is in <code>ofile</code> and all time steps are sorted by date and time. Each input file is required to have the same variables and different time steps.

Example

Assume three datasets with the same number of time steps and different variables in each dataset. To merge these datasets to a new dataset use:

```
cdo merge ifile1 ifile2 ifile3 ofile
```

Assume you split a 6 hourly dataset with [splithour](#). This produces four datasets, one for each hour. The following command merges them together:

```
cdo mergetime ifile1 ifile2 ifile3 ifile4 ofile
```

2.2.4. SPLIT - Split a dataset

Synopsis

```
<operator> ifile oprefix
```

Description

This module splits a dataset to several files with names formed from the field header information and the string **oprefix**.

Operators

splitcode	Split code numbers Splits a dataset into pieces, one for each different code number. Appends three digits with the code number to oprefix to form the output file names.
splitname	Split variable names Splits a dataset into pieces, one for each variable name. Appends a string with the variable name to oprefix to form the output file names.
splitlevel	Split levels Splits a dataset into pieces, one for each different level. Appends six digits with the level to oprefix to form the output file names.
splitgrid	Split grids Splits a dataset into pieces, one for each different grid. Appends two digits with the grid number to oprefix to form the output file names.
splitzaxis	Split z-axes Splits a dataset into pieces, one for each different z-axis. Appends two digits with the z-axis number to oprefix to form the output file names.

Example

Assume an input GRIB dataset with three variables, e.g. code number 129, 130 and 139. To split this dataset into three pieces, one for each code number use:

```
cdo splitcode ifile code
```

Result of 'dir code*':

```
code129.grb code130.grb code139.grb
```

2.2.5. SPLITTIME - Split time steps of a dataset

Synopsis

```
<operator> ifile oprefix
```

Description

This module splits time steps of a dataset to several files with names formed from the field header information and the string **oprefix**.

Operators

splithour	Split hours Splits a file into pieces, one for each different hour. Appends two digits with the hour to oprefix to form the output file names.
splitday	Split days Splits a file into pieces, one for each different day. Appends two digits with the day to oprefix to form the output file names.
splitmon	Split months Splits a file into pieces, one for each different month. Appends two digits with the month to oprefix to form the output file names.
splitseas	Split seasons Splits a file into pieces, one for each different season. Appends three characters with the season to oprefix to form the output file names.
splityear	Split years Splits a file into pieces, one for each different year. Appends four digits with the year to oprefix to form the output file names.

Example

Assume the input GRIB dataset has time steps from January to December. To split each month with all variables into one separate file use:

```
cdo splitmon ifile mon
```

Result of 'dir mon*':

```
mon01.grb  mon02.grb  mon03.grb  mon04.grb  mon05.grb  mon06.grb
mon07.grb  mon08.grb  mon09.grb  mon10.grb  mon11.grb  mon12.grb
```

2.2.6. SPLITSEL - Split selected time steps

Synopsis

```
splitsel,nsets[,noffset[,nskip]] ifile oprefix
```

Description

This operator splits a dataset into pieces, one for each adjacent sequence t_1, \dots, t_n of time steps of the same selected time range. Appends three digits with the sequence number to **oprefix** to form the output file names.

Parameter

<i>nsets</i>	INTEGER	Number of input time steps for each output file
<i>noffset</i>	INTEGER	Number of input time steps skipped before the first time step range (optional)
<i>nskip</i>	INTEGER	Number of input time steps skipped between time step ranges (optional)

2.3. Selection

This section contains modules to select time steps, fields or a part of a field from a dataset.

Here is a short overview of all operators in this section:

selcode	Select variables by code number
delcode	Delete variables by code number
selname	Select variables by name
delname	Delete variables by name
selstdname	Select variables by standard name
sellevel	Select levels
sellevidx	Select levels by index
selgrid	Select grids
selgridname	Select grids by name
selzaxis	Select z-axes
selzaxisname	Select z-axes by name
seltype	Select GRIB level types
seltabnum	Select parameter table numbers
sel timestep	Select time steps
seltime	Select times
selhour	Select hours
selday	Select days
selmon	Select months
selyear	Select years
selseas	Select seasons
seldate	Select dates
selsmon	Select single month
sellonlatbox	Select a longitude/latitude box
selindexbox	Select an index box

2.3.1. SELECT - Select fields

Synopsis

`selcode, codes ifile ofile`

`delcode, codes ifile ofile`

`selname, varnames ifile ofile`

`delname, varnames ifile ofile`

`selstdname, stdnames ifile ofile`

`sellevel, levels ifile ofile`

`sellevidx, levidx ifile ofile`

`selgrid, grids ifile ofile`

`selgridname, gridnames ifile ofile`

`selzaxis, zaxes ifile ofile`

`selzaxisname, zaxisnames ifile ofile`

`selltype, ltypes ifile ofile`

`seltabnum, tabnums ifile ofile`

Description

This module selects some fields from `ifile` and writes them to `ofile`. The fields selected depend on the chosen operator and the parameters.

Operators

selcode	Select variables by code number Selects all fields with code numbers in a user given list.
delcode	Delete variables by code number Deletes all fields with code numbers in a user given list.
selname	Select variables by name Selects all fields with variable names in a user given list.
delname	Delete variables by name Deletes all fields with variable names in a user given list.
selstdname	Select variables by standard name Selects all fields with standard names in a user given list.
sellevel	Select levels Selects all fields with levels in a user given list.
sellevidx	Select levels by index Selects all fields with index of levels in a user given list.
selgrid	Select grids Selects all fields with grids in a user given list.
selgridname	Select grids by name Selects all fields with grid names in a user given list.
selzaxis	Select z-axes Selects all fields with z-axes in a user given list.
selzaxisname	Select z-axes by name Selects all fields with z-axis names in a user given list.
selltype	Select GRIB level types Selects all fields with GRIB level type in a user given list.
seltabnum	Select parameter table numbers Selects all fields with parameter table numbers in a user given list.

Parameter

<i>codes</i>	INTEGER	Comma separated list of code numbers
<i>varnames</i>	STRING	Comma separated list of variable names
<i>stdnames</i>	STRING	Comma separated list of standard names
<i>levels</i>	FLOAT	Comma separated list of levels
<i>levidx</i>	INTEGER	Comma separated list of index of levels
<i>ltypes</i>	INTEGER	Comma separated list of GRIB level types
<i>grids</i>	INTEGER	Comma separated list of grid numbers
<i>gridnames</i>	STRING	Comma separated list of grid names
<i>zaxes</i>	INTEGER	Comma separated list of z-axis numbers
<i>zaxisnames</i>	STRING	Comma separated list of z-axis names
<i>tabnums</i>	INTEGER	Comma separated list of parameter table numbers

2.3.2. SELTIME - Select time steps

Synopsis

```

se timestep,timesteps ifile ofile

sel time,times ifile ofile

sel hour,hours ifile ofile

sel day,days ifile ofile

sel mon,months ifile ofile

sel year,years ifile ofile

sel seas,seasons ifile ofile

sel date,date1[,date2] ifile ofile

sel smon,month[,nts1[,nts2]] ifile ofile

```

Description

This module selects user specified time steps from **ifile** and writes them to **ofile**. The time steps selected depends on the chosen operator and the parameters.

Operators

se timestep	Select time steps Selects all time steps with a time step in a user given list.
sel time	Select times Selects all time steps with a time in a user given list.
sel hour	Select hours Selects all time steps with a hour in a user given list.
sel day	Select days Selects all time steps with a day in a user given list.
sel mon	Select months Selects all time steps with a month in a user given list.
sel year	Select years Selects all time steps with a year in a user given list.
sel seas	Select seasons Selects all time steps with a month of a season in a user given list.
sel date	Select dates Selects all time steps with a date in a user given range.
sel smon	Select single month Selects a month and optional an unlimited number of time steps before and after this month.

Parameter

<i>timesteps</i>	INTEGER	Comma separated list of time steps
<i>times</i>	STRING	Comma separated list of times (format hh:mm)
<i>hours</i>	INTEGER	Comma separated list of hours
<i>days</i>	INTEGER	Comma separated list of days
<i>months</i>	INTEGER	Comma separated list of months
<i>years</i>	INTEGER	Comma separated list of years
<i>seasons</i>	STRING	Comma separated list of seasons (DJF, MAM, JJA, SON)
<i>date1</i>	STRING	Start date (format YYYY-MM-DDThh:mm)
<i>date2</i>	STRING	End date (format YYYY-MM-DDThh:mm)
<i>nts1</i>	INTEGER	Number of time steps before the selected month [default: 0]
<i>nts2</i>	INTEGER	Number of time steps after the selected month [default: nts1]

2.3.3. SELBOX - Select a box of a field

Synopsis

```
sellonlatbox,lon1,lon2,lat1,lat2 ifile ofile
selindexbox,idx1,idx2,idy1,idy2 ifile ofile
```

Description

Selects a box of the rectangular understood field. All input fields need to have the same horizontal grid.

Operators

sellonlatbox	Select a longitude/latitude box Selects a longitude/latitude box. The user has to give the longitudes and latitudes of the edges of the box.
selindexbox	Select an index box Selects an index box. The user has to give the indexes of the edges of the box. The index of the left edge may be greater then that of the right edge.

Parameter

<i>lon1</i>	FLOAT	Western longitude
<i>lon2</i>	FLOAT	Eastern longitude
<i>lat1</i>	FLOAT	Southern or northern latitude
<i>lat2</i>	FLOAT	Northern or southern latitude
<i>idx1</i>	INTEGER	Index of first longitude
<i>idx2</i>	INTEGER	Index of last longitude
<i>idy1</i>	INTEGER	Index of first latitude
<i>idy2</i>	INTEGER	Index of last latitude

Example

To select the region with the longitudes from 120E to 90W and latitudes from 20N to 20S from all input fields use:

```
cdo sellonlatbox,120,-90,20,-20 ifile ofile
```

If the input dataset has fields on a T21 Gaussian grid, the same box can be selected with [selindexbox](#) by:

```
cdo selindexbox,23,48,13,20 ifile ofile
```

2.4. Conditional selection

This section contains modules to conditional select field elements. The fields in the first input file are handled as a mask. A value not equal to zero is treated as "true", zero is treated as "false".

Here is a short overview of all operators in this section:

ifthen	If then
ifnotthen	If not then
ifthenelse	If then else
ifthenc	If then constant
ifnotthenc	If not then constant

2.4.1. COND - Conditional select one field

Synopsis

```
<operator> ifile1 ifile2 ofile
```

Description

This module selects field elements from **ifile2** with respect to **ifile1** and writes them to **ofile**. The fields in **ifile1** are handled as a mask. A value not equal to zero is treated as "true", zero is treated as "false". The number of fields in **ifile1** has either to be the same as in **ifile2** or the same as in one time step of **ifile2** or only one. The fields in **ofile** inherit the meta data from **ifile2**.

Operators

ifthen	If then
	$o(t, x) = \begin{cases} i_2(t, x) & \text{if } i_1([t,]x) \neq 0 \quad \wedge \quad i_1([t,]x) \neq \text{miss} \\ \text{miss} & \text{if } i_1([t,]x) = 0 \quad \vee \quad i_1([t,]x) = \text{miss} \end{cases}$
ifnotthen	If not then
	$o(t, x) = \begin{cases} i_2(t, x) & \text{if } i_1([t,]x) = 0 \quad \wedge \quad i_1([t,]x) \neq \text{miss} \\ \text{miss} & \text{if } i_1([t,]x) \neq 0 \quad \vee \quad i_1([t,]x) = \text{miss} \end{cases}$

Example

To select all field elements of **ifile2** if the corresponding field element of **ifile1** is greater than 0 use:

```
cdo ifthen ifile1 ifile2 ofile
```

2.4.2. COND2 - Conditional select two fields

Synopsis

```
ifthenelse ifile1 ifile2 ifile3 ofile
```

Description

This operator selects field elements from **ifile2** or **ifile3** with respect to **ifile1** and writes them to **ofile**. The fields in **ifile1** are handled as a mask. A value not equal to zero is treated as "true", zero is treated as "false". The number of fields in **ifile1** has either to be the same as in **ifile2** or the same as in one time step of **ifile2** or only one. **ifile2** and **ifile3** need to have the same number of fields. The fields in **ofile** inherit the meta data from **ifile2**.

$$o(t, x) = \begin{cases} i_2(t, x) & \text{if } i_1([t,]x) \neq 0 \quad \wedge \quad i_1([t,]x) \neq \text{miss} \\ i_3(t, x) & \text{if } i_1([t,]x) = 0 \quad \wedge \quad i_1([t,]x) \neq \text{miss} \\ \text{miss} & \text{if } i_1([t,]x) = \text{miss} \end{cases}$$

Example

To select all field elements of **ifile2** if the corresponding field element of **ifile1** is greater than 0 and from **ifile3** otherwise use:

```
cdo ifthenelse ifile1 ifile2 ifile3 ofile
```

2.4.3. CONDC - Conditional select a constant

Synopsis

```
<operator>,c ifile ofile
```

Description

This module creates fields with a constant value or missing value. The fields in `ifile` are handled as a mask. A value not equal to zero is treated as "true", zero is treated as "false".

Operators

ifthenc	If then constant
	$o(t, x) = \begin{cases} c & \text{if } i(t, x) \neq 0 \wedge i(t, x) \neq \text{miss} \\ \text{miss} & \text{if } i(t, x) = 0 \vee i(t, x) = \text{miss} \end{cases}$
ifnotthenc	If not then constant
	$o(t, x) = \begin{cases} c & \text{if } i(t, x) = 0 \wedge i(t, x) \neq \text{miss} \\ \text{miss} & \text{if } i(t, x) \neq 0 \vee i(t, x) = \text{miss} \end{cases}$

Parameter

<code>c</code>	FLOAT	Constant
----------------	-------	----------

Example

To create fields with the constant value 7 if the corresponding field element of `ifile` is greater than 0 use:

```
cdo ifthenc,7 ifile ofile
```

2.5. Comparison

This section contains modules to compare datasets. The resulting field is a mask containing 1 if the comparison is true and 0 if not.

Here is a short overview of all operators in this section:

<code>eq</code>	Equal
<code>ne</code>	Not equal
<code>le</code>	Less equal
<code>lt</code>	Less than
<code>ge</code>	Greater equal
<code>gt</code>	Greater than
<code>eqc</code>	Equal constant
<code>nec</code>	Not equal constant
<code>lec</code>	Less equal constant
<code>ltc</code>	Less than constant
<code>gec</code>	Greater equal constant
<code>gtc</code>	Greater than constant

2.5.1. COMP - Comparison of two fields

Synopsis

```
<operator> ifile1 ifile2 ofile
```

Description

This module compares two datasets field by field. The resulting field is a mask containing 1 if the comparison is true and 0 if not. The number of fields in `ifile1` should be the same as in `ifile2`. One of the input files can contain only one time step or one field. The fields in `ofile` inherit the meta data from `ifile1` or `ifile2`. The type of comparison depends on the chosen operator.

Operators

eq	Equal	$o(t, x) = \begin{cases} 1 & \text{if } i_1(t, x) = i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ 0 & \text{if } i_1(t, x) \neq i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ \text{miss} & \text{if } i_1(t, x) = \text{miss} \quad \vee \quad i_2(t, x) = \text{miss} \end{cases}$
ne	Not equal	$o(t, x) = \begin{cases} 1 & \text{if } i_1(t, x) \neq i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ 0 & \text{if } i_1(t, x) = i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ \text{miss} & \text{if } i_1(t, x) = \text{miss} \quad \vee \quad i_2(t, x) = \text{miss} \end{cases}$
le	Less equal	$o(t, x) = \begin{cases} 1 & \text{if } i_1(t, x) \leq i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ 0 & \text{if } i_1(t, x) > i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ \text{miss} & \text{if } i_1(t, x) = \text{miss} \quad \vee \quad i_2(t, x) = \text{miss} \end{cases}$
lt	Less than	$o(t, x) = \begin{cases} 1 & \text{if } i_1(t, x) < i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ 0 & \text{if } i_1(t, x) \geq i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ \text{miss} & \text{if } i_1(t, x) = \text{miss} \quad \vee \quad i_2(t, x) = \text{miss} \end{cases}$
ge	Greater equal	$o(t, x) = \begin{cases} 1 & \text{if } i_1(t, x) \geq i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ 0 & \text{if } i_1(t, x) < i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ \text{miss} & \text{if } i_1(t, x) = \text{miss} \quad \vee \quad i_2(t, x) = \text{miss} \end{cases}$
gt	Greater than	$o(t, x) = \begin{cases} 1 & \text{if } i_1(t, x) > i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ 0 & \text{if } i_1(t, x) \leq i_2(t, x) \quad \wedge \quad i_1(t, x), i_2(t, x) \neq \text{miss} \\ \text{miss} & \text{if } i_1(t, x) = \text{miss} \quad \vee \quad i_2(t, x) = \text{miss} \end{cases}$

Example

To create a mask containing 1 if the elements of two fields are the same and 0 if the elements are different use:

```
cdo eq ifile1 ifile2 ofile
```


2.5.2. COMPC - Comparison of a field with a constant

Synopsis

`<operator>,c ifile ofile`

Description

This module compares all fields of a dataset with a constant. The resulting field is a mask containing 1 if the comparison is true and 0 if not. The type of comparison depends on the chosen operator.

Operators

eqc Equal constant

$$o(t, x) = \begin{cases} 1 & \text{if } i(t, x) = c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ 0 & \text{if } i(t, x) \neq c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ \text{miss} & \text{if } i(t, x) = \text{miss} \quad \vee \quad c = \text{miss} \end{cases}$$

nec Not equal constant

$$o(t, x) = \begin{cases} 1 & \text{if } i(t, x) \neq c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ 0 & \text{if } i(t, x) = c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ \text{miss} & \text{if } i(t, x) = \text{miss} \quad \vee \quad c = \text{miss} \end{cases}$$

lec Less equal constant

$$o(t, x) = \begin{cases} 1 & \text{if } i(t, x) \leq c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ 0 & \text{if } i(t, x) > c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ \text{miss} & \text{if } i(t, x) = \text{miss} \quad \vee \quad c = \text{miss} \end{cases}$$

ltc Less than constant

$$o(t, x) = \begin{cases} 1 & \text{if } i(t, x) < c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ 0 & \text{if } i(t, x) \geq c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ \text{miss} & \text{if } i(t, x) = \text{miss} \quad \vee \quad c = \text{miss} \end{cases}$$

gec Greater equal constant

$$o(t, x) = \begin{cases} 1 & \text{if } i(t, x) \geq c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ 0 & \text{if } i(t, x) < c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ \text{miss} & \text{if } i(t, x) = \text{miss} \quad \vee \quad c = \text{miss} \end{cases}$$

gtc Greater than constant

$$o(t, x) = \begin{cases} 1 & \text{if } i(t, x) > c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ 0 & \text{if } i(t, x) \leq c \quad \wedge \quad i(t, x), c \neq \text{miss} \\ \text{miss} & \text{if } i(t, x) = \text{miss} \quad \vee \quad c = \text{miss} \end{cases}$$

Parameter

c FLOAT Constant

Example

To create a mask containing 1 if the field element is greater than 273.15 and 0 if not use:

```
cdo gtc,273.15 ifile ofile
```

2.6. Modification

This section contains modules to modify the metadata, fields or part of a field in a dataset.

Here is a short overview of all operators in this section:

setpartab	Set parameter table
setcode	Set code number
setname	Set variable name
setlevel	Set level
setltype	Set GRIB level type
setdate	Set date
settime	Set time of the day
setday	Set day
setmon	Set month
setyear	Set year
settunits	Set time units
settaxis	Set time axis
setreftime	Set reference time
setcalendar	Set calendar
shifttime	Shift time steps
chcode	Change code number
chname	Change variable name
chlevel	Change level
chlevelc	Change level of one code
chlevelv	Change level of one variable
setgrid	Set grid
setgridtype	Set grid type
setzaxis	Set z-axis
setgatt	Set global attribute
setgatts	Set global attributes
invertlat	Invert latitudes
invertlev	Invert levels
maskregion	Mask regions
masklonlatbox	Mask a longitude/latitude box
maskindexbox	Mask an index box
setclonlatbox	Set a longitude/latitude box to constant
setcindexbox	Set an index box to constant
enlarge	Enlarge fields
setmissval	Set a new missing value
setctomiss	Set constant to missing value
setmisstoc	Set missing value to constant
setrtomiss	Set range to missing value

2.6.1. SET - Set field info

Synopsis

```
setpartab,table ifile ofile
setcode,code ifile ofile
setname,name ifile ofile
setlevel,level ifile ofile
setltype,ltype ifile ofile
```

Description

This module sets some field information. Depending on the chosen operator the parameter table, code number, variable name or level is set.

Operators

setpartab	Set parameter table Sets the parameter table for all variables.
setcode	Set code number Sets the code number for all variables to the same given value.
setname	Set variable name Sets the name of the first variable.
setlevel	Set level Sets the first level of all variables.
setltype	Set GRIB level type Sets the GRIB level type of all variables.

Parameter

<i>table</i>	STRING	Parameter table file or name
<i>code</i>	INTEGER	Code number
<i>name</i>	STRING	Variable name
<i>level</i>	FLOAT	New level
<i>ltype</i>	INTEGER	GRIB level type

Example

To assign the parameter table echam5 to the input dataset use:

```
cdo setpartab ,echam5 ifile ofile
```

2.6.2. SETTIME - Set time

Synopsis

```

setdate,date ifile ofile
settime,time ifile ofile
setday,day ifile ofile
setmon,month ifile ofile
setyear,year ifile ofile
settunits,units ifile ofile
settaxis,date,time[,inc] ifile ofile
setreftime,date,time ifile ofile
setcalendar,calendar ifile ofile
shifttime,sval ifile ofile

```

Description

This module sets the time axis or part of the time axis. Which part of the time axis is overwritten depends on the chosen operator.

Operators

setdate	Set date Sets the date in every time step to the same given value.
settime	Set time of the day Sets the time in every time step to the same given value.
setday	Set day Sets the day in every time step to the same given value.
setmon	Set month Sets the month in every time step to the same given value.
setyear	Set year Sets the year in every time step to the same given value.
settunits	Set time units Sets the base units of a relative time axis.
settaxis	Set time axis Sets the time axis.
setreftime	Set reference time Sets the reference time of a relative time axis.
setcalendar	Set calendar Sets the calendar of a relative time axis.
shifttime	Shift time steps Shifts all time steps by the parameter sval.

Parameter

<i>day</i>	INTEGER	Value of the new day
<i>month</i>	INTEGER	Value of the new month
<i>year</i>	INTEGER	Value of the new year
<i>units</i>	STRING	Base units of the time axis (minutes, hours, days, months, years)
<i>date</i>	STRING	Date (format YYYY-MM-DD)
<i>time</i>	STRING	Time (format HH:MM)
<i>inc</i>	STRING	Optional increment (minutes, hours, days, months, years) [default: 0hour]
<i>calendar</i>	STRING	Calendar (standard, 360days, 365days, 366days)
<i>sval</i>	STRING	Shift value (e.g. -3hour)

Example

To set the time axis to 1987-01-16 12:00 with an increment of one month for each time step use:

```
cdo settaxis,1987-01-16,12:00,1mon ifile ofile
```

Result of 'cdo showdate ofile' for a dataset with 12 time steps:

```
1987-01-16 1987-02-16 1987-03-16 1987-04-16 1987-05-16 1987-06-16 \
1987-07-16 1987-08-16 1987-09-16 1987-10-16 1987-11-16 1987-12-16
```

To shift this time axis by -15 days use:

```
cdo shifttime,-15days ifile ofile
```

Result of 'cdo showdate ofile':

```
1987-01-01 1987-02-01 1987-03-01 1987-04-01 1987-05-01 1987-06-01 \
1987-07-01 1987-08-01 1987-09-01 1987-10-01 1987-11-01 1987-12-01
```

2.6.3. CHANGE - Change field header

Synopsis

```

chcode,oldcode,newcode[,...] ifile ofile
chname,oldname,newname,... ifile ofile
chlevel,oldlev,newlev,... ifile ofile
chlevelc,code,oldlev,newlev ifile ofile
chlevelv,name,oldlev,newlev ifile ofile

```

Description

This module reads fields from **ifile**, changes some header values and writes the results to **ofile**. The kind of changes depends on the chosen operator.

Operators

chcode	Change code number Changes some user given code numbers to new user given values.
chname	Change variable name Changes some user given variable names to new user given names.
chlevel	Change level Changes some user given levels to new user given values.
chlevelc	Change level of one code Changes one level of a user given code number.
chlevelv	Change level of one variable Changes one level of a user given variable name.

Parameter

<i>code</i>	INTEGER	Code number
<i>oldcode</i> , <i>newcode</i> ,...	INTEGER	Pairs of old and new code numbers
<i>name</i>	STRING	Variable name
<i>oldname</i> , <i>newname</i> ,...	STRING	Pairs of old and new variable names
<i>oldlev</i>	FLOAT	Old level
<i>newlev</i>	FLOAT	New level
<i>oldlev</i> , <i>newlev</i> ,...	FLOAT	Pairs of old and new levels

Example

To change the code number 98 to 179 and 99 to 211 use:

```
cdo chcode,98,179,99,211 ifile ofile
```

2.6.4. SETGRID - Set grid type

Synopsis

```
setgrid,grid ifile ofile
setgridtype,gridtype ifile ofile
```

Description

This module sets the grid description of all fields with the same grid size as the new grid.

Operators

setgrid	Set grid Sets the grid description of all fields.
setgridtype	Set grid type Sets the grid type of all grids to a user given value.

Parameter

<i>grid</i>	STRING	Target grid description file or name
<i>gridtype</i>	STRING	Target grid type (curvilinear or cell)

Example

Assuming a dataset has fields with 2048 gridpoints without or with wrong grid description. To set the grid description of all input fields to a T21 Gaussian grid (2048 gridpoints) use:

```
cdo setgrid ,t21grid ifile ofile
```

2.6.5. SETZAXIS - Set z-axis type

Synopsis

```
setzaxis,zaxis ifile ofile
```

Description

This operator sets the z-axis description of all variables with the same number of level as the new z-axis.

Parameter

<i>zaxis</i>	STRING	Z-axis description file or name of the target z-axis
--------------	--------	--

2.6.6. SETGATT - Set global attribute

Synopsis

```
setgatt,attname,attstring ifile ofile
setgatts,attfile ifile ofile
```

Description

This module sets global text attributes of a dataset. Depending on the chosen operator the attributes are read from a file or can be specified by a parameter.

Operators

setgatt	Set global attribute Sets one user defined global text attribute.
setgatts	Set global attributes Sets user defined global text attributes. The name and text of the global attributes are read from a file.

Parameter

<i>attname,attstring</i>	STRING	Name and text of the global attribute (without spaces!)
<i>attfile</i>	STRING	File name which contains global text attributes

Note

Besides netCDF none of the supported data formats supports global attributes.

Example

To set the global text attribute "myatt" to "myattcontents" in a netCDF file use:

```
cdo setgatt ,myatt,myattcontents ifile ofile
```

Result of 'ncdump -h ofile':

```
netcdf ofile {
dimensions: ...

variables: ...

// global attributes:
           :myatt = "myattcontents" ;
}
```


2.6.7. INVERT - Invert latitudes

Synopsis

```
invertlat ifile ofile
```

Description

This operator inverts the latitudes of all fields with a regular rectangular grid.

Example

To invert the latitudes of a 2D field from N->S to S->N use:

```
cdo invertlat ifile ofile
```

2.6.8. INVERTLEV - Invert levels

Synopsis

```
invertlev ifile ofile
```

Description

This operator inverts the levels of all non hybrid 3D variables.

2.6.9. MASKREGION - Mask regions

Synopsis

```
maskregion,regions ifile ofile
```

Description

Masks different regions of a field. The elements inside a region are untouched, the elements outside are set to missing value. All input fields need to have the same horizontal grid. The user has to give ASCII formatted files with different regions. A region is defined by a polygon. Each line of a polygon description file contains the longitude and latitude of one point. Each polygon description file can contain one or more polygons separated by a line with the character &.

Parameter

<i>regions</i>	STRING	Comma separated list of ASCII formatted files with different regions
----------------	--------	--

Example

To mask the region with the longitudes from 120E to 90W and latitudes from 20N to 20S on all input fields use:

```
cdo maskregion,myregion ifile ofile
```

For this example the polygon description file `myregion` should contain the following four coordinates:

```
120 20
120 -20
270 -20
270 20
```

2.6.10. MASKBOX - Mask a box

Synopsis

```
masklonlatbox,lon1,lon2,lat1,lat2 ifile ofile
```

```
maskindexbox,idx1,idx2,idy1,idy2 ifile ofile
```

Description

Masks a box of the rectangular understood field. The elements inside the box are untouched, the elements outside are set to missing value. All input fields need to have the same horizontal grid. Use [sellonlatbox](#) or [selindexbox](#) if only the data inside the box are needed.

Operators

masklonlatbox	Mask a longitude/latitude box Masks a longitude/latitude box. The user has to give the longitudes and latitudes of the edges of the box.
maskindexbox	Mask an index box Masks an index box. The user has to give the indexes of the edges of the box. The index of the left edge can be greater then the one of the right edge.

Parameter

<i>lon1</i>	FLOAT	Western longitude
<i>lon2</i>	FLOAT	Eastern longitude
<i>lat1</i>	FLOAT	Southern or northern latitude
<i>lat2</i>	FLOAT	Northern or southern latitude
<i>idx1</i>	INTEGER	Index of first longitude
<i>idx2</i>	INTEGER	Index of last longitude
<i>idy1</i>	INTEGER	Index of first latitude
<i>idy2</i>	INTEGER	Index of last latitude

Example

To mask the region with the longitudes from 120E to 90W and latitudes from 20N to 20S on all input fields use:

```
cdo masklonlatbox,120,-90,20,-20 ifile ofile
```

If the input dataset has fields on a T21 Gaussian grid, the same box can be masked with [maskindexbox](#) by:

```
cdo maskindexbox,23,48,13,20 ifile ofile
```

2.6.11. SETBOX - Set a box to constant

Synopsis

```
setclonlatbox,c,lon1,lon2,lat1,lat2 ifile ofile
```

```
setcindexbox,c,idx1,idx2,idy1,idy2 ifile ofile
```

Description

Sets a box of the rectangular understood field to a constant value. The elements outside the box are untouched, the elements inside are set to the given constant. All input fields need to have the same horizontal grid.

Operators

setclonlatbox	Set a longitude/latitude box to constant Sets the values of a longitude/latitude box to a constant value. The user has to give the longitudes and latitudes of the edges of the box.
setcindexbox	Set an index box to constant Sets the values of an index box to a constant value. The user has to give the indexes of the edges of the box. The index of the left edge can be greater than the one of the right edge.

Parameter

<i>c</i>	FLOAT	Constant
<i>lon1</i>	FLOAT	Western longitude
<i>lon2</i>	FLOAT	Eastern longitude
<i>lat1</i>	FLOAT	Southern or northern latitude
<i>lat2</i>	FLOAT	Northern or southern latitude
<i>idx1</i>	INTEGER	Index of first longitude
<i>idx2</i>	INTEGER	Index of last longitude
<i>idy1</i>	INTEGER	Index of first latitude
<i>idy2</i>	INTEGER	Index of last latitude

Example

To set all values in the region with the longitudes from 120E to 90W and latitudes from 20N to 20S to the constant value -1.23 use:

```
cdo setclonlatbox,-1.23,120,-90,20,-20 ifile ofile
```

If the input dataset has fields on a T21 Gaussian grid, the same box can be set with [setcindexbox](#) by:

```
cdo setcindexbox,-1.23,23,48,13,20 ifile ofile
```

2.6.12. ENLARGE - Enlarge fields

Synopsis

```
enlarge,grid ifile ofile
```

Description

Enlarge all fields of `ifile` to a user given grid. Normally only the last field element is used for the enlargement. If however the input and output grid are rectangular, a zonal or meridional enlargement is possible. Zonal enlargement takes place, if the `xsize` of the input field is 1 and the `ysize` of both grids are the same. For meridional enlargement the `ysize` have to be 1 and the `xsize` of both grids should have the same size.

Parameter

<i>grid</i>	STRING	Target grid description file or name
-------------	--------	--------------------------------------

Example

Assumed you want to add two datasets. The first dataset is on a T21 grid (2048 field elements) and the second dataset is only a global mean (1 field element). Before you can add these two datasets the second dataset have to be enlarged to the grid size of the first dataset:

```
cdo enlarge ,t21grid ifile2 tmpfile
cdo add ifile1 tmpfile ofile
```

Or shorter using operator piping:

```
cdo add ifile1 -enlarge ,t21grid ifile2 ofile
```

2.6.13. SETMISS - Set missing value

Synopsis

```
setmissval,newmiss ifile ofile
setctomiss,c ifile ofile
setmisstoc,c ifile ofile
setrtomiss,rmin,rmax ifile ofile
```

Description

This module sets part of a field to missing value or missing values to a constant value. Which part of the field is set depends on the chosen operator.

Operators

setmissval Set a new missing value

$$o(t, x) = \begin{cases} \text{newmiss} & \text{if } i(t, x) = \text{miss} \\ i(t, x) & \text{if } i(t, x) \neq \text{miss} \end{cases}$$

setctomiss Set constant to missing value

$$o(t, x) = \begin{cases} \text{miss} & \text{if } i(t, x) = c \\ i(t, x) & \text{if } i(t, x) \neq c \end{cases}$$

setmisstoc Set missing value to constant

$$o(t, x) = \begin{cases} c & \text{if } i(t, x) = \text{miss} \\ i(t, x) & \text{if } i(t, x) \neq \text{miss} \end{cases}$$

setrtomiss Set range to missing value

$$o(t, x) = \begin{cases} \text{miss} & \text{if } i(t, x) \geq rmin \wedge i(t, x) \leq rmax \\ i(t, x) & \text{if } i(t, x) < rmin \vee i(t, x) > rmax \end{cases}$$

Parameter

<i>newmiss</i>	FLOAT	New missing value
<i>c</i>	FLOAT	Constant
<i>rmin</i>	FLOAT	Lower bound
<i>rmax</i>	FLOAT	Upper bound

Example

Assume an input dataset has one field with temperatures in the range from 246 to 304 Kelvin. To set all values below 273.15 Kelvin to missing value use:

```
cdo setrtomiss ,0,273.15 ifile ofile
```

Result of 'cdo info ifile':

-1 :	Date	Time	Code	Level	Size	Miss :	Minimum	Mean	Maximum
1 :	1987-12-31	12:00	139	0	2048	0 :	246.27	276.75	303.71

Result of 'cdo info ofile':

-1 :	Date	Time	Code	Level	Size	Miss :	Minimum	Mean	Maximum
1 :	1987-12-31	12:00	139	0	2048	871 :	273.16	287.08	303.71

2.7. Arithmetic

This section contains modules to arithmetically process datasets.

Here is a short overview of all operators in this section:

expr	Evaluate expressions
exprf	Evaluate expressions from script file
abs	Absolute value
int	Integer value
nint	Nearest integer value
pow	Power
sqr	Square
sqrt	Square root
exp	Exponential
ln	Natural logarithm
log10	Base 10 logarithm
sin	Sine
cos	Cosine
tan	Tangent
asin	Arc sine
acos	Arc cosine
atan	Arc tangent
addc	Add a constant
subc	Subtract a constant
mulc	Multiply with a constant
divc	Divide by a constant
add	Add two fields
sub	Subtract two fields
mul	Multiply two fields
div	Divide two fields
min	Minimum of two fields
max	Maximum of two fields
atan2	Arc tangent of two fields
monadd	Add monthly time series
monsub	Subtract monthly time series
monmul	Multiply monthly time series
monddiv	Divide monthly time series
ymonadd	Add multi-year monthly time series
ymonsub	Subtract multi-year monthly time series
ymonmul	Multiply multi-year monthly time series
ymonddiv	Divide multi-year monthly time series
muldpm	Multiply with days per month
divdpm	Divide by days per month
muldpy	Multiply with days per year
divdpy	Divide by days per year

2.7.1. EXPR - Evaluate expressions

Synopsis

```
expr,instr ifile ofile
exprf,filename ifile ofile
```

Description

This module arithmetically processes every time step of the input dataset. Each individual assignment statement have to end with a semi-colon. The basic arithmetic operations addition +, subtraction −, multiplication *, division / and exponentiation ^ can be used. The following intrinsic functions are available:

<code>sqrt(x)</code>	Square Root of x
<code>exp(x)</code>	Exponential of x
<code>log(x)</code>	Natural logarithm of x
<code>log10(x)</code>	Base 10 logarithm of x
<code>sin(x)</code>	Sine of x, where x is specified in radians
<code>cos(x)</code>	Cosine of x, where x is specified in radians
<code>tan(x)</code>	Tangent of x, where x is specified in radians
<code>asin(x)</code>	Arc-sine of x, where x is specified in radians
<code>acos(x)</code>	Arc-cosine of x, where x is specified in radians
<code>atan(x)</code>	Arc-tangent of x, where x is specified in radians

Operators

expr	Evaluate expressions The processing instructions are read from the parameter.
exprf	Evaluate expressions from script file Contrary to expr the processing instructions are read from a file.

Parameter

<i>instr</i>	STRING	Processing instructions (without spaces!)
<i>filename</i>	STRING	File with processing instructions

Example

Assume an input dataset contains at least the variables 'aprl', 'aprc' and 'ts'. To create a new variable 'var1' with the sum of 'aprl' and 'aprc' and a variable 'var2' which convert the temperature 'ts' from Kelvin to Celsius use:

```
cdo expr, 'var1=aprl+aprc; var2=ts - 273.15;' ifile ofile
```

The same example, but the instructions are read from a file:

```
cdo exprf, myexpr ifile ofile
```

The file `myexpr` contains:

```
var1 = aprl + aprc;
var2 = ts - 273.15;
```


2.7.2. MATH - Mathematical functions

Synopsis

`<operator> ifile ofile`

Description

This module contains some standard mathematical functions. All trigonometric functions calculate with radians.

Operators

abs	Absolute value $o(t, x) = \text{abs}(i(t, x))$
int	Integer value $o(t, x) = \text{int}(i(t, x))$
nint	Nearest integer value $o(t, x) = \text{nint}(i(t, x))$
pow	Power $o(t, x) = i(t, x)^y$
sqr	Square $o(t, x) = i(t, x)^2$
sqrt	Square root $o(t, x) = \sqrt{i(t, x)}$
exp	Exponential $o(t, x) = e^{i(t, x)}$
ln	Natural logarithm $o(t, x) = \ln(i(t, x))$
log10	Base 10 logarithm $o(t, x) = \log_{10}(i(t, x))$
sin	Sine $o(t, x) = \sin(i(t, x))$
cos	Cosine $o(t, x) = \cos(i(t, x))$
tan	Tangent $o(t, x) = \tan(i(t, x))$
asin	Arc sine $o(t, x) = \arcsin(i(t, x))$
acos	Arc cosine $o(t, x) = \arccos(i(t, x))$
atan	Arc tangent $o(t, x) = \arctan(i(t, x))$

Example

To calculate the square root for all field elements use:

```
cdo sqrt ifile ofile
```

2.7.3. ARITHC - Arithmetic with a constant

Synopsis

```
<operator>,c ifile ofile
```

Description

This module performs simple arithmetic with all field elements of a dataset and a constant. The fields in `ofile` inherit the meta data from `ifile`.

Operators

addc	Add a constant $o(t, x) = i(t, x) + c$
subc	Subtract a constant $o(t, x) = i(t, x) - c$
mulc	Multiply with a constant $o(t, x) = i(t, x) * c$
divc	Divide by a constant $o(t, x) = i(t, x) / c$

Parameter

<code>c</code>	FLOAT	Constant
----------------	-------	----------

Example

To sum all input fields with the constant -273.15 use:

```
cdo addc,-273.15 ifile ofile
```

2.7.4. ARITH - Arithmetic on two datasets

Synopsis

`<operator> ifile1 ifile2 ofile`

Description

This module performs simple arithmetic of two datasets. The number of fields in `ifile1` should be the same as in `ifile2`. One of the input files can contain only one time step or one field. The fields in `ofile` inherit the meta data from `ifile1` or `ifile2`.

Operators

add	Add two fields $o(t, x) = i_1(t, x) + i_2(t, x)$
sub	Subtract two fields $o(t, x) = i_1(t, x) - i_2(t, x)$
mul	Multiply two fields $o(t, x) = i_1(t, x) * i_2(t, x)$
div	Divide two fields $o(t, x) = i_1(t, x) / i_2(t, x)$
min	Minimum of two fields $o(t, x) = \min(i_1(t, x), i_2(t, x))$
max	Maximum of two fields $o(t, x) = \max(i_1(t, x), i_2(t, x))$
atan2	Arc tangent of two fields The <i>atan2</i> operator calculates the arc tangent of two fields. The result is in radians, which is between -PI and PI (inclusive). $o(t, x) = \text{atan2}(i_1(t, x), i_2(t, x))$

Example

To sum all fields of the first input file with the corresponding fields of the second input file use:

```
cdo add ifile1 ifile2 ofile
```

2.7.5. MONARITH - Monthly arithmetic

Synopsis

```
<operator> ifile1 ifile2 ofile
```

Description

This module performs simple arithmetic of a time series and one time step with the same month and year. For each field in `ifile1` the corresponding field of the time step in `ifile2` with the same month and year is used. The header information in `ifile1` have to be the same as in `ifile2`. Usually `ifile2` is generated by a call of the module [MONSTAT](#).

Operators

monadd	Add monthly time series Adds a time series and a monthly time series.
monsub	Subtract monthly time series Subtracts a time series and a monthly time series.
monmul	Multiply monthly time series Multiplies a time series and a monthly time series.
monddiv	Divide monthly time series Divides a time series and a monthly time series.

Example

To subtract a monthly time average from a time series use:

```
cdo monsub ifile -monavg ifile ofile
```

2.7.6. YMONARITH - Multi-year monthly arithmetic

Synopsis

```
<operator> ifile1 ifile2 ofile
```

Description

This module performs simple arithmetic of a time series and one time step with the same month of year. For each field in `ifile1` the corresponding field of the time step in `ifile2` with the same month of year is used. The header information in `ifile1` have to be the same as in `ifile2`. Usually `ifile2` is generated by a call of the module [YMONSTAT](#).

Operators

ymonadd	Add multi-year monthly time series Adds a time series and a multi-year monthly time series.
ymonsub	Subtract multi-year monthly time series Subtracts a time series and a multi-year monthly time series.
ymonmul	Multiply multi-year monthly time series Multiplies a time series and a multi-year monthly time series.
ymonddiv	Divide multi-year monthly time series Divides a time series and a multi-year monthly time series.

Example

To subtract a multi-year monthly time average from a time series use:

```
cdo ymonsub ifile -ymonavg ifile ofile
```

2.7.7. ARITHDAYS - Arithmetic with days

Synopsis

`<operator> ifile ofile`

Description

This module multiplies or divides each time step of a dataset with the corresponding days per month or days per year.

Operators

muldpm	Multiply with days per month $o(t, x) = i(t, x) * days_per_month$
divdpm	Divide by days per month $o(t, x) = i(t, x) / days_per_month$
muldpy	Multiply with days per year $o(t, x) = i(t, x) * days_per_year$
divdpy	Divide by days per year $o(t, x) = i(t, x) / days_per_year$

Example

Assume an input dataset is a monthly mean time series. To compute the yearly mean from the correct weighted monthly mean use:

```
cdo muldpm ifile tmpfile1
cdo yearavg tmpfile1 tmpfile2
cdo mulc,12 -divdpy tmpfile2 ofile
```

Or all in one command line:

```
cdo mulc,12 -divdpy -yearavg -muldpm ifile ofile
```

2.8. Statistical values

This section contains modules to compute statistical values of datasets. In this program there is the different notion of "mean" and "average" to distinguish two different kinds of treatment of missing values. While computing the mean, only the not missing values are considered to belong to the sample with the side effect of a probably reduced sample size. Computing the average is just adding the sample members and divide the result by the sample size. For example, the mean of 1, 2, miss and 3 is $(1+2+3)/3 = 2$, whereas the average is $(1+2+miss+3)/4 = miss/4 = miss$. If there are no missing values in the sample, the average and the mean are identical.

In this section the abbreviations as in the following table are used:

sum	$\sum_{i=1}^n x_i$
mean resp. avg	$n^{-1} \sum_{i=1}^n x_i$
mean resp. avg weighted by $\{w_i, i = 1, \dots, n\}$	$\left(\sum_{j=1}^n w_j \right)^{-1} \sum_{i=1}^n w_i x_i$
Variance var	$n^{-1} \sum_{i=1}^n (x_i - \bar{x})^2$
var weighted by $\{w_i, i = 1, \dots, n\}$	$\left(\sum_{j=1}^n w_j \right)^{-1} \sum_{i=1}^n w_i \left(x_i - \left(\sum_{j=1}^n w_j \right)^{-1} \sum_{j=1}^n w_j x_j \right)^2$
Standard deviation std	$\sqrt{n^{-1} \sum_{i=1}^n (x_i - \bar{x})^2}$
std weighted by $\{w_i, i = 1, \dots, n\}$	$\sqrt{\left(\sum_{j=1}^n w_j \right)^{-1} \sum_{i=1}^n w_i \left(x_i - \left(\sum_{j=1}^n w_j \right)^{-1} \sum_{j=1}^n w_j x_j \right)^2}$

Here is a short overview of all operators in this section:

ensmin	Ensemble minimum
ensmax	Ensemble maximum
enssum	Ensemble sum
ensmean	Ensemble mean
ensavg	Ensemble average
ensvar	Ensemble variance
ensstd	Ensemble standard deviation
enspctl	Ensemble percentiles

fldmin	Field minimum
fldmax	Field maximum
fldsum	Field sum
fldmean	Field mean
fldavg	Field average
fldvar	Field variance
fldstd	Field standard deviation
fldpctl	Field percentiles
zonmin	Zonal minimum
zonmax	Zonal maximum
zonsum	Zonal sum
zonmean	Zonal mean
zonavg	Zonal average
zonvar	Zonal variance
zonstd	Zonal standard deviation
zonpctl	Zonal percentiles
mermin	Meridional minimum
mermax	Meridional maximum
mersum	Meridional sum
mermean	Meridional mean
meravg	Meridional average
mervar	Meridional variance
merstd	Meridional standard deviation
merpctl	Meridional percentiles
vertmin	Vertical minimum
vertmax	Vertical maximum
vertsum	Vertical sum
vertmean	Vertical mean
vertavg	Vertical average
vertvar	Vertical variance
vertstd	Vertical standard deviation
timselmin	Time range minimum
timselmax	Time range maximum
timselsum	Time range sum
timselmean	Time range mean
timselavg	Time range average
timselvar	Time range variance
timselstd	Time range standard deviation
timselpctl	Time range percentiles
runmin	Running minimum
runmax	Running maximum
runsum	Running sum
runmean	Running mean
runavg	Running average
runvar	Running variance
runstd	Running standard deviation
runpctl	Running percentiles

timmin	Time minimum
timmax	Time maximum
timsum	Time sum
timmean	Time mean
timavg	Time average
timvar	Time variance
timstd	Time standard deviation
timctl	Time percentiles
hourmin	Hourly minimum
hourmax	Hourly maximum
hoursum	Hourly sum
hourmean	Hourly mean
houravg	Hourly average
hourvar	Hourly variance
hourstd	Hourly standard deviation
hourctl	Hourly percentiles
daymin	Daily minimum
daymax	Daily maximum
daysum	Daily sum
daymean	Daily mean
dayavg	Daily average
dayvar	Daily variance
daystd	Daily standard deviation
dayctl	Daily percentiles
monmin	Monthly minimum
monmax	Monthly maximum
monsum	Monthly sum
monmean	Monthly mean
monavg	Monthly average
monvar	Monthly variance
monstd	Monthly standard deviation
monctl	Monthly percentiles
yearmin	Yearly minimum
yearmax	Yearly maximum
yearsum	Yearly sum
yearmean	Yearly mean
yearavg	Yearly average
yearvar	Yearly variance
yearstd	Yearly standard deviation
yearctl	Yearly percentiles
seasmin	Seasonal minimum
seasmax	Seasonal maximum
seassum	Seasonal sum
seasmean	Seasonal mean
seasavg	Seasonal average
seasvar	Seasonal variance
seasstd	Seasonal standard deviation

seaspctl	Seasonal percentiles
yhourmin	Multi-year hourly minimum
yhourmax	Multi-year hourly maximum
yhoursum	Multi-year hourly sum
yhourmean	Multi-year hourly mean
yhouravg	Multi-year hourly average
yhourvar	Multi-year hourly variance
yhourstd	Multi-year hourly standard deviation
ydaymin	Multi-year daily minimum
ydaymax	Multi-year daily maximum
ydaysum	Multi-year daily sum
ydaymean	Multi-year daily mean
ydayavg	Multi-year daily average
ydayvar	Multi-year daily variance
ydaystd	Multi-year daily standard deviation
ydaypctl	Multi-year daily percentiles
ymonmin	Multi-year monthly minimum
ymonmax	Multi-year monthly maximum
ymonsum	Multi-year monthly sum
ymonmean	Multi-year monthly mean
ymonavg	Multi-year monthly average
ymonvar	Multi-year monthly variance
ymonstd	Multi-year monthly standard deviation
ymonpctl	Multi-year monthly percentiles
yseasmin	Multi-year seasonal minimum
yseasmax	Multi-year seasonal maximum
yseasum	Multi-year seasonal sum
yseasmean	Multi-year seasonal mean
yseasavg	Multi-year seasonal average
yseasvar	Multi-year seasonal variance
yseasstd	Multi-year seasonal standard deviation
yseaspctl	Multi-year seasonal percentiles
ydrunmin	Multi-year daily running minimum
ydrunmax	Multi-year daily running maximum
ydrunsum	Multi-year daily running sum
ydrunmean	Multi-year daily running mean
ydrunavg	Multi-year daily running average
ydrunvar	Multi-year daily running variance
ydrunstd	Multi-year daily running standard deviation
ydrunpctl	Multi-year daily running percentiles

2.8.1. ENSSTAT - Statistical values over an ensemble

Synopsis

```

ensmin ifiles ofile
ensmax ifiles ofile
enssum ifiles ofile
ensmean ifiles ofile
ensavg ifiles ofile
ensvar ifiles ofile
ensstd ifiles ofile
enspctl,p ifiles ofile

```

Description

This module computes statistical values over an ensemble of input files. Depending on the chosen operator the minimum, maximum, sum, average, variance, standard deviation, or a certain percentile over all input files is written to `ofile`. The date information of a time step in `ofile` is the date of the first input file.

Operators

ensmin	Ensemble minimum $o(t, x) = \mathbf{min}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$
ensmax	Ensemble maximum $o(t, x) = \mathbf{max}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$
enssum	Ensemble sum $o(t, x) = \mathbf{sum}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$
ensmean	Ensemble mean $o(t, x) = \mathbf{mean}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$
ensavg	Ensemble average $o(t, x) = \mathbf{avg}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$
ensvar	Ensemble variance $o(t, x) = \mathbf{var}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$
ensstd	Ensemble standard deviation $o(t, x) = \mathbf{std}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$
enspctl	Ensemble percentiles $o(t, x) = \mathbf{pth\ percentile}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$

Parameter

p INTEGER Percentile number in 1, ..., 99

Example

To compute the ensemble mean over 6 input files use:

```
cdo ensmean ifile1 ifile2 ifile3 ifile4 ifile5 ifile6 ofile
```

Or shorter with filename substitution:

```
cdo ensmean ifile[1-6] ofile
```

To compute the 50th percentile (median) over 6 input files use:

```
cdo enspctl,50 ifile1 ifile2 ifile3 ifile4 ifile5 ifile6 ofile
```

Or shorter with filename substitution:

```
cdo enspctl,50 ifile[1-6] ofile
```

2.8.2. FLDSTAT - Statistical values over a field

Synopsis

```
fldmin ifile ofile
fldmax ifile ofile
fldsum ifile ofile
fldmean ifile ofile
fldavg ifile ofile
fldvar ifile ofile
fldstd ifile ofile
fldpctl,p ifile ofile
```

Description

This module computes statistical values of the input fields. According to the chosen operator the field minimum, maximum, sum, average, variance, standard deviation or a certain percentile is written to ofile.

Operators

fldmin	Field minimum For every gridpoint x_1, \dots, x_n of the same field it is: $o(t, 1) = \mathbf{min}\{i(t, x'), x_1 < x' \leq x_n\}$
fldmax	Field maximum For every gridpoint x_1, \dots, x_n of the same field it is: $o(t, 1) = \mathbf{max}\{i(t, x'), x_1 < x' \leq x_n\}$
fldsum	Field sum For every gridpoint x_1, \dots, x_n of the same field it is: $o(t, 1) = \mathbf{sum}\{i(t, x'), x_1 < x' \leq x_n\}$
fldmean	Field mean For every gridpoint x_1, \dots, x_n of the same field it is: $o(t, 1) = \mathbf{mean}\{i(t, x'), x_1 < x' \leq x_n\}$ weighted by area weights obtained by the input field.
fldavg	Field average For every gridpoint x_1, \dots, x_n of the same field it is: $o(t, 1) = \mathbf{avg}\{i(t, x'), x_1 < x' \leq x_n\}$ weighted by area weights obtained by the input field.
fldvar	Field variance For every gridpoint x_1, \dots, x_n of the same field it is: $o(t, 1) = \mathbf{var}\{i(t, x'), x_1 < x' \leq x_n\}$ weighted by area weights obtained by the input field.
fldstd	Field standard deviation For every gridpoint x_1, \dots, x_n of the same field it is: $o(t, 1) = \mathbf{std}\{i(t, x'), x_1 < x' \leq x_n\}$ weighted by area weights obtained by the input field.
fldpctl	Field percentiles For every gridpoint x_1, \dots, x_n of the same field it is: $o(t, 1) = \mathbf{pth\ percentile}\{i(t, x'), x_1 < x' \leq x_n\}$

Parameter

p INTEGER Percentile number in 1, ..., 99

Example

To compute the field mean of all input fields use:

```
cdo fldmean ifile ofile
```

To compute the 90th percentile of all input fields use:

```
cdo fldpctl,90 ifile ofile
```

2.8.3. ZONSTAT - Zonal statistical values

Synopsis

```

zonmin ifile ofile

zonmax ifile ofile

zonsum ifile ofile

zonmean ifile ofile

zonavg ifile ofile

zonvar ifile ofile

zonstd ifile ofile

zonpctl,p ifile ofile

```

Description

This module computes zonal statistical values of the input fields. According to the chosen operator the zonal minimum, maximum, sum, average, variance, standard deviation or a certain percentile is written to ofile. All input fields need to have the same rectangular grid.

Operators

zonmin	Zonal minimum For every latitude the minimum over all longitudes is computed.
zonmax	Zonal maximum For every latitude the maximum over all longitudes is computed.
zonsum	Zonal sum For every latitude the sum over all longitudes is computed.
zonmean	Zonal mean For every latitude the mean over all longitudes is computed.
zonavg	Zonal average For every latitude the average over all longitudes is computed.
zonvar	Zonal variance For every latitude the variance over all longitudes is computed.
zonstd	Zonal standard deviation For every latitude the standard deviation over all longitudes is computed.
zonpctl	Zonal percentiles For every latitude the pth percentile over all longitudes is computed.

Parameter

p INTEGER Percentile number in 1, ..., 99

Example

To compute the zonal mean of all input fields use:

```
cdo zonmean ifile ofile
```

To compute the 50th meridional percentile (median) of all input fields use:

```
cdo zonpctl,50 ifile ofile
```


2.8.4. MERSTAT - Meridional statistical values

Synopsis

```

mermin ifile ofile
mermax ifile ofile
mersum ifile ofile
mermean ifile ofile
meravg ifile ofile
mervar ifile ofile
merstd ifile ofile
merpctl,p ifile ofile

```

Description

This module computes meridional statistical values of the input fields. According to the chosen operator the meridional minimum, maximum, sum, average, variance, standard deviation or a certain percentile is written to `ofile`. All input fields need to have the same rectangular grid.

Operators

mermin	Meridional minimum For every longitude the minimum over all latitudes is computed.
mermax	Meridional maximum For every longitude the maximum over all latitudes is computed.
mersum	Meridional sum For every longitude the sum over all latitudes is computed.
mermean	Meridional mean For every longitude the area weighted mean over all latitudes is computed.
meravg	Meridional average For every longitude the area weighted average over all latitudes is computed.
mervar	Meridional variance For every longitude the variance over all latitudes is computed.
merstd	Meridional standard deviation For every longitude the standard deviation over all latitudes is computed.
merpctl	Meridional percentiles For every longitude the <i>p</i> th percentile over all latitudes is computed.

Parameter

p INTEGER Percentile number in 1, ..., 99

Example

To compute the meridional mean of all input fields use:

```
cdo mermean ifile ofile
```

To compute the 50th meridional percentile (median) of all input fields use:

```
cdo merpctl,50 ifile ofile
```

2.8.5. VERTSTAT - Vertical statistical values

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values over all levels of the input variables. According to chosen operator the vertical minimum, maximum, sum, average, variance or standard deviation is written to ofile.

Operators

vertmin	Vertical minimum For every gridpoint the minimum over all levels is computed.
vertmax	Vertical maximum For every gridpoint the maximum over all levels is computed.
vertsum	Vertical sum For every gridpoint the sum over all levels is computed.
vertmean	Vertical mean For every gridpoint the mean over all levels is computed.
vertavg	Vertical average For every gridpoint the average over all levels is computed.
vertvar	Vertical variance For every gridpoint the variance over all levels is computed.
vertstd	Vertical standard deviation For every gridpoint the standard deviation over all levels is computed.

Example

To compute the vertical sum of all input variables use:

```
cdo vertsum ifile ofile
```

2.8.6. TIMSELSTAT - Time range statistical values

Synopsis

```
<operator>,nsets[,noffset[,nskip]] ifile ofile
```

Description

This module computes statistical values for a selected number of time steps. According to the chosen operator the minimum, maximum, sum, average, variance or standard deviation of the selected time steps is written to `ofile`. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Operators

timselmin	Time range minimum For every adjacent sequence t_1, \dots, t_n of time steps of the same selected time range it is: $o(t, x) = \min\{i(t', x), t_1 < t' \leq t_n\}$
timselmax	Time range maximum For every adjacent sequence t_1, \dots, t_n of time steps of the same selected time range it is: $o(t, x) = \max\{i(t', x), t_1 < t' \leq t_n\}$
timselsum	Time range sum For every adjacent sequence t_1, \dots, t_n of time steps of the same selected time range it is: $o(t, x) = \sum\{i(t', x), t_1 < t' \leq t_n\}$
timselmean	Time range mean For every adjacent sequence t_1, \dots, t_n of time steps of the same selected time range it is: $o(t, x) = \text{mean}\{i(t', x), t_1 < t' \leq t_n\}$
timselavg	Time range average For every adjacent sequence t_1, \dots, t_n of time steps of the same selected time range it is: $o(t, x) = \text{avg}\{i(t', x), t_1 < t' \leq t_n\}$
timselvar	Time range variance For every adjacent sequence t_1, \dots, t_n of time steps of the same selected time range it is: $o(t, x) = \text{var}\{i(t', x), t_1 < t' \leq t_n\}$
timselstd	Time range standard deviation For every adjacent sequence t_1, \dots, t_n of time steps of the same selected time range it is: $o(t, x) = \text{std}\{i(t', x), t_1 < t' \leq t_n\}$

Parameter

<i>nsets</i>	INTEGER	Number of input time steps for each output time step
<i>noffset</i>	INTEGER	Number of input time steps skipped before the first time step range (optional)
<i>nskip</i>	INTEGER	Number of input time steps skipped between time step ranges (optional)

Example

Assume an input dataset has monthly means over several years. To compute seasonal means from monthly means the first two month have to be skipped:

```
cdo timselmean,3,2 ifile ofile
```

2.8.7. TIMSELPCTL - Time range percentile values

Synopsis

```
timselpctl,p,nsets[,noffset[,nskip]] ifile1 ifile2 ifile3 ofile
```

Description

This operator computes percentile values over a selected number of time steps in `ifile1`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `timselmin` and `timselmax` operations, respectively. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

For every adjacent sequence t_1, \dots, t_n of time steps of the same selected time range it is:

$$o(t, x) = \text{pth percentile}\{i(t', x), t_1 < t' \leq t_n\}$$

Parameter

<i>p</i>	INTEGER	Percentile number in 1, ..., 99
<i>nsets</i>	INTEGER	Number of input time steps for each output time step
<i>noffset</i>	INTEGER	Number of input time steps skipped before the first time step range (optional)
<i>nskip</i>	INTEGER	Number of input time steps skipped between time step ranges (optional)

Environment

<code>CDO_PCTL_NBINS</code>	Sets the number of histogram bins. The default number is 100.
-----------------------------	---

2.8.8. RUNSTAT - Running statistical values

Synopsis

```
<operator>,nts ifile ofile
```

Description

This module computes running statistical values over a selected number of time steps. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of a selected number of consecutive time steps read from **ifile** is written to **ofile**. The date information in **ofile** is the date of the middle contributing time step in **ifile**.

Operators

runmin	Running minimum $o(t + (nts - 1)/2, x) = \min\{i(t, x), i(t + 1, x), \dots, i(t + nts - 1, x)\}$
runmax	Running maximum $o(t + (nts - 1)/2, x) = \max\{i(t, x), i(t + 1, x), \dots, i(t + nts - 1, x)\}$
runsum	Running sum $o(t + (nts - 1)/2, x) = \text{sum}\{i(t, x), i(t + 1, x), \dots, i(t + nts - 1, x)\}$
runmean	Running mean $o(t + (nts - 1)/2, x) = \text{mean}\{i(t, x), i(t + 1, x), \dots, i(t + nts - 1, x)\}$
runavg	Running average $o(t + (nts - 1)/2, x) = \text{avg}\{i(t, x), i(t + 1, x), \dots, i(t + nts - 1, x)\}$
runvar	Running variance $o(t + (nts - 1)/2, x) = \text{std}\{i(t, x), i(t + 1, x), \dots, i(t + nts - 1, x)\}$
runstd	Running standard deviation $o(t + (nts - 1)/2, x) = \text{std}\{i(t, x), i(t + 1, x), \dots, i(t + nts - 1, x)\}$

Parameter

nts INTEGER Number of time steps

Environment

RUNSTAT_DATE Sets the date information in ofile to the "first", "last" or "middle" contributing time step in ifile.

Example

To compute the running mean over 9 time steps use:

```
cdo runmean,9 ifile ofile
```

2.8.9. RUNPCTL - Running percentile values

Synopsis

```
runpctl,p,nts ifile1 ofile
```

Description

This module computes running percentiles over a selected number of time steps in **ifile1**. The date information in **ofile** is the date of the medium contributing time step in **ifile1**.

$$o(t + (nts - 1)/2, x) = \mathbf{pth\ percentile}\{i(t, x), i(t + 1, x), \dots, i(t + nts - 1, x)\}$$

Parameter

<i>p</i>	INTEGER	Percentile number in 1, ..., 99
<i>nts</i>	INTEGER	Number of time steps

Example

To compute the running 50th percentile (median) over 9 time steps use:

```
cdo runpctl,50,9 ifile -runmin,9 ifile -runmax,9 ifile ofile
```

2.8.10. TIMSTAT - Statistical values over all time steps

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values over all time steps in **ifile**. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of all time steps read from **ifile** is written to **ofile**. The date information of a time step in **ofile** is the date of the last contributing time step in **ifile**.

Operators

timmin	Time minimum $o(1, x) = \mathbf{min}\{i(t', x), t_1 < t' \leq t_n\}$
timmax	Time maximum $o(1, x) = \mathbf{max}\{i(t', x), t_1 < t' \leq t_n\}$
timsum	Time sum $o(1, x) = \mathbf{sum}\{i(t', x), t_1 < t' \leq t_n\}$
timmean	Time mean $o(1, x) = \mathbf{mean}\{i(t', x), t_1 < t' \leq t_n\}$
timavg	Time average $o(1, x) = \mathbf{avg}\{i(t', x), t_1 < t' \leq t_n\}$
timvar	Time variance $o(1, x) = \mathbf{var}\{i(t', x), t_1 < t' \leq t_n\}$
timstd	Time standard deviation $o(1, x) = \mathbf{std}\{i(t', x), t_1 < t' \leq t_n\}$

Example

To compute the mean over all input time steps use:

```
cdo timmean ifile ofile
```


2.8.11. TIMPCTL - Percentile values over all time steps

Synopsis

```
timpctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator computes percentiles over all time steps in `ifile1`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `timmin` and `timmax` operations, respectively. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

$$o(1, x) = \text{pth percentile}\{i(t', x), t_1 < t' \leq t_n\}$$

Parameter

p INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the 90th percentile over all input time steps use:

```
cdo timmin ifile minfile
cdo timmax ifile maxfile
cdo timpctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo timpctl,90 ifile -timmin ifile -timmax ifile ofile
```

2.8.12. HOURSTAT - Hourly statistical values

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values over time steps of the same hour. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of time steps of the same hour is written to `ofile`. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Operators

hourmin	Hourly minimum For every adjacent sequence t_1, \dots, t_n of time steps of the same hour it is: $o(t, x) = \mathbf{min}\{i(t', x), t_1 < t' \leq t_n\}$
hourmax	Hourly maximum For every adjacent sequence t_1, \dots, t_n of time steps of the same hour it is: $o(t, x) = \mathbf{max}\{i(t', x), t_1 < t' \leq t_n\}$
hoursum	Hourly sum For every adjacent sequence t_1, \dots, t_n of time steps of the same hour it is: $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \leq t_n\}$
hourmean	Hourly mean For every adjacent sequence t_1, \dots, t_n of time steps of the same hour it is: $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \leq t_n\}$
houravg	Hourly average For every adjacent sequence t_1, \dots, t_n of time steps of the same hour it is: $o(t, x) = \mathbf{avg}\{i(t', x), t_1 < t' \leq t_n\}$
hourvar	Hourly variance For every adjacent sequence t_1, \dots, t_n of time steps of the same hour it is: $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \leq t_n\}$
hourstd	Hourly standard deviation For every adjacent sequence t_1, \dots, t_n of time steps of the same hour it is: $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \leq t_n\}$

Example

To compute the hourly mean of a time series use:

```
cdo hourmean ifile ofile
```

2.8.13. HOURPCTL - Hourly percentile values

Synopsis

```
hourpctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator computes percentiles over all time steps of the same hour in `ifile1`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `hourmin` and `hourmax` operations, respectively. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

For every adjacent sequence t_1, \dots, t_n of time steps of the same hour it is:

$$o(t, x) = \text{pth percentile}\{i(t', x), t_1 < t' \leq t_n\}$$

Parameter

p INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the hourly 90th percentile of a time series use:

```
cdo hourmin ifile minfile
cdo hourmax ifile maxfile
cdo hourpctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo hourpctl,90 ifile -hourmin ifile -hourmax ifile ofile
```

2.8.14. DAYSTAT - Daily statistical values

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values over time steps of the same day. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of time steps of the same day is written to `ofile`. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Operators

daymin	Daily minimum For every adjacent sequence t_1, \dots, t_n of time steps of the same day it is: $o(t, x) = \mathbf{min}\{i(t', x), t_1 < t' \leq t_n\}$
daymax	Daily maximum For every adjacent sequence t_1, \dots, t_n of time steps of the same day it is: $o(t, x) = \mathbf{max}\{i(t', x), t_1 < t' \leq t_n\}$
daysum	Daily sum For every adjacent sequence t_1, \dots, t_n of time steps of the same day it is: $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \leq t_n\}$
daymean	Daily mean For every adjacent sequence t_1, \dots, t_n of time steps of the same day it is: $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \leq t_n\}$
dayavg	Daily average For every adjacent sequence t_1, \dots, t_n of time steps of the same day it is: $o(t, x) = \mathbf{avg}\{i(t', x), t_1 < t' \leq t_n\}$
dayvar	Daily variance For every adjacent sequence t_1, \dots, t_n of time steps of the same day it is: $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \leq t_n\}$
daystd	Daily standard deviation For every adjacent sequence t_1, \dots, t_n of time steps of the same day it is: $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \leq t_n\}$

Example

To compute the daily mean of a time series use:

```
cdo daymean ifile ofile
```

2.8.15. DAYPCTL - Daily percentile values

Synopsis

```
daypctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator computes percentiles over all time steps of the same day in `ifile1`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by defining the environment variable `CDO_PCTL_NBINS`. The files `ifile2` and `ifile3` should be the result of corresponding `daymin` and `daymax` operations, respectively. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

For every adjacent sequence t_1, \dots, t_n of time steps of the same day it is:

$$o(t, x) = \text{pth percentile}\{i(t', x), t_1 < t' \leq t_n\}$$

Parameter

`p` INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the daily 90th percentile of a time series use:

```
cdo daymin ifile minfile
cdo daymax ifile maxfile
cdo daypctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo daypctl,90 ifile -daymin ifile -daymax ifile ofile
```

2.8.16. MONSTAT - Monthly statistical values

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values over time steps of the same month. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of time steps of the same month is written to `ofile`. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Operators

monmin	Monthly minimum For every adjacent sequence t_1, \dots, t_n of time steps of the same month it is: $o(t, x) = \mathbf{min}\{i(t', x), t_1 < t' \leq t_n\}$
monmax	Monthly maximum For every adjacent sequence t_1, \dots, t_n of time steps of the same month it is: $o(t, x) = \mathbf{max}\{i(t', x), t_1 < t' \leq t_n\}$
monsum	Monthly sum For every adjacent sequence t_1, \dots, t_n of time steps of the same month it is: $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \leq t_n\}$
monmean	Monthly mean For every adjacent sequence t_1, \dots, t_n of time steps of the same month it is: $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \leq t_n\}$
monavg	Monthly average For every adjacent sequence t_1, \dots, t_n of time steps of the same month it is: $o(t, x) = \mathbf{avg}\{i(t', x), t_1 < t' \leq t_n\}$
monvar	Monthly variance For every adjacent sequence t_1, \dots, t_n of time steps of the same month it is: $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \leq t_n\}$
monstd	Monthly standard deviation For every adjacent sequence t_1, \dots, t_n of time steps of the same month it is: $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \leq t_n\}$

Example

To compute the monthly mean of a time series use:

```
cdo monmean ifile ofile
```

2.8.17. MONPCTL - Monthly percentile values

Synopsis

```
monpctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator computes percentiles over all time steps of the same month in `ifile1`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `monmin` and `monmax` operations, respectively. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

For every adjacent sequence t_1, \dots, t_n of time steps of the same month it is:

$$o(t, x) = \text{pth percentile}\{i(t', x), t_1 < t' \leq t_n\}$$

Parameter

`p` INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the monthly 90th percentile of a time series use:

```
cdo monmin ifile minfile
cdo monmax ifile maxfile
cdo monpctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo monpctl,90 ifile -monmin ifile -monmax ifile ofile
```

2.8.18. YEARSTAT - Yearly statistical values

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values over time steps of the same year. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of time steps of the same year is written to `ofile`. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Operators

yearmin	Yearly minimum For every adjacent sequence t_1, \dots, t_n of time steps of the same year it is: $o(t, x) = \mathbf{min}\{i(t', x), t_1 < t' \leq t_n\}$
yearmax	Yearly maximum For every adjacent sequence t_1, \dots, t_n of time steps of the same year it is: $o(t, x) = \mathbf{max}\{i(t', x), t_1 < t' \leq t_n\}$
yearsum	Yearly sum For every adjacent sequence t_1, \dots, t_n of time steps of the same year it is: $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \leq t_n\}$
yearmean	Yearly mean For every adjacent sequence t_1, \dots, t_n of time steps of the same year it is: $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \leq t_n\}$
yearavg	Yearly average For every adjacent sequence t_1, \dots, t_n of time steps of the same year it is: $o(t, x) = \mathbf{avg}\{i(t', x), t_1 < t' \leq t_n\}$
yearvar	Yearly variance For every adjacent sequence t_1, \dots, t_n of time steps of the same year it is: $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \leq t_n\}$
yearstd	Yearly standard deviation For every adjacent sequence t_1, \dots, t_n of time steps of the same year it is: $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \leq t_n\}$

Note

The operators `yearmean` and `yearavg` compute only arithmetical means!

Example

To compute the yearly mean of a time series use:

```
cdo yearmean ifile ofile
```

To compute the yearly mean from the correct weighted monthly mean use:

```
cdo mulc,12 -divdpy -yearmean -muldpm ifile ofile
```


2.8.19. YEARPCTL - Yearly percentile values

Synopsis

```
yearpctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator computes percentiles over all time steps of the same year in `ifile1`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `yearmin` and `yearmax` operations, respectively. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

For every adjacent sequence t_1, \dots, t_n of time steps of the same year it is:

$$o(t, x) = \text{pth percentile}\{i(t', x), t_1 < t' \leq t_n\}$$

Parameter

`p` INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the yearly 90th percentile of a time series use:

```
cdo yearmin ifile minfile
cdo yearmax ifile maxfile
cdo yearpctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo yearpctl,90 ifile -yearmin ifile -yearmax ifile ofile
```

2.8.20. SEASSTAT - Seasonal statistical values

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values over time steps of the same season. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of time steps of the same season is written to `ofile`. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`. Be careful about the first and the last output time step, they may be incorrect values if the seasons have incomplete time steps.

Operators

seasmin	Seasonal minimum For every adjacent sequence t_1, \dots, t_n of time steps of the same season it is: $o(t, x) = \mathbf{min}\{i(t', x), t_1 < t' \leq t_n\}$
seasmax	Seasonal maximum For every adjacent sequence t_1, \dots, t_n of time steps of the same season it is: $o(t, x) = \mathbf{max}\{i(t', x), t_1 < t' \leq t_n\}$
seassum	Seasonal sum For every adjacent sequence t_1, \dots, t_n of time steps of the same season it is: $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \leq t_n\}$
seasmean	Seasonal mean For every adjacent sequence t_1, \dots, t_n of time steps of the same season it is: $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \leq t_n\}$
seasavg	Seasonal average For every adjacent sequence t_1, \dots, t_n of time steps of the same season it is: $o(t, x) = \mathbf{avg}\{i(t', x), t_1 < t' \leq t_n\}$
seasvar	Seasonal variance For every adjacent sequence t_1, \dots, t_n of time steps of the same season it is: $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \leq t_n\}$
seasstd	Seasonal standard deviation For every adjacent sequence t_1, \dots, t_n of time steps of the same season it is: $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \leq t_n\}$

Example

To compute the seasonal mean of a time series use:

```
cdo seasmean ifile ofile
```

2.8.21. SEASPCTL - Seasonal percentile values

Synopsis

```
seaspctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator computes percentiles over all time steps in `ifile1` of the same season. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `seasmin` and `seasmax` operations, respectively. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`. Be careful about the first and the last output time step, they may be incorrect values if the seasons have incomplete time steps.

For every adjacent sequence t_1, \dots, t_n of time steps of the same season it is:

$$o(t, x) = \text{pth percentile}\{i(t', x), t_1 < t' \leq t_n\}$$

Parameter

`p` INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the seasonal 90th percentile of a time series use:

```
cdo seasmin ifile minfile
cdo seasmax ifile maxfile
cdo seaspctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo seaspctl,90 ifile -seasmin ifile -seasmax ifile ofile
```

2.8.22. YHOURSTAT - Multi-year hourly statistical values

Synopsis

`<operator> ifile ofile`

Description

This module computes statistical values of each hour and day of year. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of each hour and day of year in `ifile` is written to `ofile`. The date information in an output field is the date of the last contributing input field.

Operators

yhourmin	Multi-year hourly minimum $o(0001, x) = \min\{i(t, x), \text{day}(i(t)) = 0001\}$ \vdots $o(8784, x) = \min\{i(t, x), \text{day}(i(t)) = 8784\}$
yhourmax	Multi-year hourly maximum $o(0001, x) = \max\{i(t, x), \text{day}(i(t)) = 0001\}$ \vdots $o(8784, x) = \max\{i(t, x), \text{day}(i(t)) = 8784\}$
yhoursum	Multi-year hourly sum $o(0001, x) = \text{sum}\{i(t, x), \text{day}(i(t)) = 0001\}$ \vdots $o(8784, x) = \text{sum}\{i(t, x), \text{day}(i(t)) = 8784\}$
yhourmean	Multi-year hourly mean $o(0001, x) = \text{mean}\{i(t, x), \text{day}(i(t)) = 0001\}$ \vdots $o(8784, x) = \text{mean}\{i(t, x), \text{day}(i(t)) = 8784\}$
yhouravg	Multi-year hourly average $o(0001, x) = \text{avg}\{i(t, x), \text{day}(i(t)) = 0001\}$ \vdots $o(8784, x) = \text{avg}\{i(t, x), \text{day}(i(t)) = 8784\}$
yhourvar	Multi-year hourly variance $o(0001, x) = \text{var}\{i(t, x), \text{day}(i(t)) = 0001\}$ \vdots $o(8784, x) = \text{var}\{i(t, x), \text{day}(i(t)) = 8784\}$
yhourstd	Multi-year hourly standard deviation $o(0001, x) = \text{std}\{i(t, x), \text{day}(i(t)) = 0001\}$ \vdots $o(8784, x) = \text{std}\{i(t, x), \text{day}(i(t)) = 8784\}$

Example

To compute the hourly mean for all days over all input years use:

```
cdo yhourmean ifile ofile
```

2.8.23. YDAYSTAT - Multi-year daily statistical values

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values of each day of year. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of each day of year in `ifile` is written to `ofile`. The date information in an output field is the date of the last contributing input field.

Operators

ydaymin	Multi-year daily minimum $o(001, x) = \min\{i(t, x), \text{day}(i(t)) = 001\}$ \vdots $o(366, x) = \min\{i(t, x), \text{day}(i(t)) = 366\}$
ydaymax	Multi-year daily maximum $o(001, x) = \max\{i(t, x), \text{day}(i(t)) = 001\}$ \vdots $o(366, x) = \max\{i(t, x), \text{day}(i(t)) = 366\}$
ydaysum	Multi-year daily sum $o(001, x) = \text{sum}\{i(t, x), \text{day}(i(t)) = 001\}$ \vdots $o(366, x) = \text{sum}\{i(t, x), \text{day}(i(t)) = 366\}$
ydaymean	Multi-year daily mean $o(001, x) = \text{mean}\{i(t, x), \text{day}(i(t)) = 001\}$ \vdots $o(366, x) = \text{mean}\{i(t, x), \text{day}(i(t)) = 366\}$
ydayavg	Multi-year daily average $o(001, x) = \text{avg}\{i(t, x), \text{day}(i(t)) = 001\}$ \vdots $o(366, x) = \text{avg}\{i(t, x), \text{day}(i(t)) = 366\}$
ydayvar	Multi-year daily variance $o(001, x) = \text{var}\{i(t, x), \text{day}(i(t)) = 001\}$ \vdots $o(366, x) = \text{var}\{i(t, x), \text{day}(i(t)) = 366\}$
ydaystd	Multi-year daily standard deviation $o(001, x) = \text{std}\{i(t, x), \text{day}(i(t)) = 001\}$ \vdots $o(366, x) = \text{std}\{i(t, x), \text{day}(i(t)) = 366\}$

Example

To compute the daily mean over all input years use:

```
cdo ydaymean ifile ofile
```

2.8.24. YDAYPCTL - Multi-year daily percentile values

Synopsis

```
ydaypctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator writes a certain percentile of each day of year in `ifile1` to `ofile`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `ydaymin` and `ydaymax` operations, respectively. The date information in an output field is the date of the last contributing input field.

$$\begin{aligned} o(001, x) &= \text{pth percentile}\{i(t, x), \text{day}(i(t)) = 001\} \\ &\vdots \\ o(366, x) &= \text{pth percentile}\{i(t, x), \text{day}(i(t)) = 366\} \end{aligned}$$

Parameter

`p` INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the daily 90th percentile over all input years use:

```
cdo ydaymin ifile minfile
cdo ydaymax ifile maxfile
cdo ydaypctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo ydaypctl,90 ifile -ydaymin ifile -ydaymax ifile ofile
```

2.8.25. YMONSTAT - Multi-year monthly statistical values

Synopsis

```
<operator> ifile ofile
```

Description

This module computes statistical values of each month of year. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of each month of year in **ifile** is written to **ofile**. The date information in an output field is the date of the last contributing input field.

Operators

ymonmin	Multi-year monthly minimum $o(01, x) = \min\{i(t, x), \text{month}(i(t)) = 01\}$ \vdots $o(12, x) = \min\{i(t, x), \text{month}(i(t)) = 12\}$
ymonmax	Multi-year monthly maximum $o(01, x) = \max\{i(t, x), \text{month}(i(t)) = 01\}$ \vdots $o(12, x) = \max\{i(t, x), \text{month}(i(t)) = 12\}$
ymonsum	Multi-year monthly sum $o(01, x) = \text{sum}\{i(t, x), \text{month}(i(t)) = 01\}$ \vdots $o(12, x) = \text{sum}\{i(t, x), \text{month}(i(t)) = 12\}$
ymonmean	Multi-year monthly mean $o(01, x) = \text{mean}\{i(t, x), \text{month}(i(t)) = 01\}$ \vdots $o(12, x) = \text{mean}\{i(t, x), \text{month}(i(t)) = 12\}$
ymonavg	Multi-year monthly average $o(01, x) = \text{avg}\{i(t, x), \text{month}(i(t)) = 01\}$ \vdots $o(12, x) = \text{avg}\{i(t, x), \text{month}(i(t)) = 12\}$
ymonvar	Multi-year monthly variance $o(01, x) = \text{var}\{i(t, x), \text{month}(i(t)) = 01\}$ \vdots $o(12, x) = \text{var}\{i(t, x), \text{month}(i(t)) = 12\}$
ymonstd	Multi-year monthly standard deviation $o(01, x) = \text{std}\{i(t, x), \text{month}(i(t)) = 01\}$ \vdots $o(12, x) = \text{std}\{i(t, x), \text{month}(i(t)) = 12\}$

Example

To compute the monthly mean over all input years use:

```
cdo ymonmean ifile ofile
```

2.8.26. YMONPCTL - Multi-year monthly percentile values

Synopsis

```
ymonpctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator writes a certain percentile of each month of year in `ifile1` to `ofile`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `ymonmin` and `ymonmax` operations, respectively. The date information in an output field is the date of the last contributing input field.

$$o(01, x) = \text{pth percentile}\{i(t, x), \text{month}(i(t)) = 01\}$$

$$\vdots$$

$$o(12, x) = \text{pth percentile}\{i(t, x), \text{month}(i(t)) = 12\}$$

Parameter

p INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the monthly 90th percentile over all input years use:

```
cdo ymonmin ifile minfile
cdo ymonmax ifile maxfile
cdo ymonpctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo ymonpctl,90 ifile -ymonmin ifile -ymonmax ifile ofile
```


2.8.27. YSEASSTAT - Multi-year seasonal statistical values

Synopsis

`<operator> ifile ofile`

Description

This module computes statistical values of each season. Depending on the chosen operator the minimum, maximum, sum, average, variance or standard deviation of each season in `ifile` is written to `ofile`. The date information in an output field is the date of the last contributing input field.

Operators

yseasmin	Multi-year seasonal minimum $o(1, x) = \min\{i(t, x), \text{month}(i(t)) = 12, 01, 02\}$ $o(2, x) = \min\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}$ $o(3, x) = \min\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}$ $o(4, x) = \min\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}$
yseasmax	Multi-year seasonal maximum $o(1, x) = \max\{i(t, x), \text{month}(i(t)) = 12, 01, 02\}$ $o(2, x) = \max\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}$ $o(3, x) = \max\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}$ $o(4, x) = \max\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}$
yseassum	Multi-year seasonal sum $o(1, x) = \text{sum}\{i(t, x), \text{month}(i(t)) = 12, 01, 02\}$ $o(2, x) = \text{sum}\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}$ $o(3, x) = \text{sum}\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}$ $o(4, x) = \text{sum}\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}$
yseasmean	Multi-year seasonal mean $o(1, x) = \text{mean}\{i(t, x), \text{month}(i(t)) = 12, 01, 02\}$ $o(2, x) = \text{mean}\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}$ $o(3, x) = \text{mean}\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}$ $o(4, x) = \text{mean}\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}$
yseasavg	Multi-year seasonal average $o(1, x) = \text{avg}\{i(t, x), \text{month}(i(t)) = 12, 01, 02\}$ $o(2, x) = \text{avg}\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}$ $o(3, x) = \text{avg}\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}$ $o(4, x) = \text{avg}\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}$
yseasvar	Multi-year seasonal variance $o(1, x) = \text{var}\{i(t, x), \text{month}(i(t)) = 12, 01, 02\}$ $o(2, x) = \text{var}\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}$ $o(3, x) = \text{var}\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}$ $o(4, x) = \text{var}\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}$
yseasstd	Multi-year seasonal standard deviation $o(1, x) = \text{std}\{i(t, x), \text{month}(i(t)) = 12, 01, 02\}$ $o(2, x) = \text{std}\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}$ $o(3, x) = \text{std}\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}$ $o(4, x) = \text{std}\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}$

Example

To compute the seasonal mean over all input years use:

```
cdo yseasmean ifile ofile
```

2.8.28. YSEASPCTL - Multi-year seasonal percentile values

Synopsis

```
yseaspctl,p ifile1 ifile2 ifile3 ofile
```

Description

This operator writes a certain percentile of each season in `ifile1` to `ofile`. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `yseasmin` and `yseasmax` operations, respectively. The date information in an output field is the date of the last contributing input field.

$$\begin{aligned} o(1, x) &= \text{pth percentile}\{i(t, x), \text{month}(i(t)) = 12, 01, 02\} \\ o(2, x) &= \text{pth percentile}\{i(t, x), \text{month}(i(t)) = 03, 04, 05\} \\ o(3, x) &= \text{pth percentile}\{i(t, x), \text{month}(i(t)) = 06, 07, 08\} \\ o(4, x) &= \text{pth percentile}\{i(t, x), \text{month}(i(t)) = 09, 10, 11\} \end{aligned}$$

Parameter

`p` INTEGER Percentile number in 1, ..., 99

Environment

`CDO_PCTL_NBINS` Sets the number of histogram bins. The default number is 100.

Example

To compute the seasonal 90th percentile over all input years use:

```
cdo yseasmin ifile minfile
cdo yseasmax ifile maxfile
cdo yseaspctl,90 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo yseaspctl,90 ifile -yseasmin ifile -yseasmax ifile ofile
```

2.8.29. YDRUNSTAT - Multi-year daily running statistical values

Synopsis

`<operator>,nts ifile ofile`

Description

This module writes running statistical values for each day of year in `ifile` to `ofile`. Depending on the chosen operator, the minimum, maximum, sum, average, variance or standard deviation of all time steps in running windows of which the medium time step corresponds to a certain day of year is computed. The date information in an output field is the date of the medium time step in the last contributing running window. Note that the operator have to be applied to a continuous time series of daily measurements in order to yield physically meaningful results. Also note that the output time series begins $(nts-1)/2$ time steps after the first time step of the input time series and ends $(nts-1)/2$ time steps before the last one. For input data which are complete but not continuous, such as time series of daily measurements for the same month or season within different years, the operator yields physically meaningful results only if the input time series does include the $(nts-1)/2$ days before and after each period of interest.

Operators

ydrunmin	Multi-year daily running minimum $o(001, x) = \min\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 001\}$ \vdots $o(366, x) = \min\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 366\}$
ydrunmax	Multi-year daily running maximum $o(001, x) = \max\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 001\}$ \vdots $o(366, x) = \max\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 366\}$
ydrunsum	Multi-year daily running sum $o(001, x) = \sum\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 001\}$ \vdots $o(366, x) = \sum\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 366\}$
ydrunmean	Multi-year daily running mean $o(001, x) = \text{mean}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 001\}$ \vdots $o(366, x) = \text{mean}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 366\}$
ydrunavg	Multi-year daily running average $o(001, x) = \text{avg}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 001\}$ \vdots $o(366, x) = \text{avg}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 366\}$
ydrunvar	Multi-year daily running variance $o(001, x) = \text{var}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 001\}$ \vdots $o(366, x) = \text{var}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 366\}$
ydrunstd	Multi-year daily running standard deviation $o(001, x) = \text{std}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 001\}$ \vdots $o(366, x) = \text{std}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 366\}$

Parameter

nts INTEGER Number of time steps

Example

Assume the input data provide a continuous time series of daily measurements. To compute the running multi-year daily mean over all input time steps for a running window of five days use:

```
cdo ydrunmean,5 ifile ofile
```

Note that except for the standard deviation the results of the operators in this module are equivalent to a composition of corresponding operators from the [YDAYSTAT](#) and [RUNSTAT](#) modules. For instance, the above command yields the same result as:

```
cdo ydaymean -runmean,5 ifile ofile
```

2.8.30. YDRUNPCTL - Multi-year daily running percentile values

Synopsis

```
ydrunctl,p,nts ifile1 ifile2 ifile3 ofile
```

Description

This operator writes running percentile values for each day of year in `ifile1` to `ofile`. A certain percentile is computed for all time steps in running windows of which the medium time step corresponds to a certain day of year. The algorithm uses histograms with minimum and maximum bounds given in `ifile2` and `ifile3`, respectively. The default number of histogram bins is 100. The default can be overridden by setting the environment variable `CDO_PCTL_NBINS` to a different value. The files `ifile2` and `ifile3` should be the result of corresponding `ydrunmin` and `ydrunmax` operations, respectively. The date information in an output field is the date of the medium time step in the last contributing running window. Note that the operator have to be applied to a continuous time series of daily measurements in order to yield physically meaningful results. Also note that the output time series begins $(nts-1)/2$ time steps after the first time step of the input time series and ends $(nts-1)/2$ time steps before the last. For input data which are complete but not continuous, such as time series of daily measurements for the same month or season within different years, the operator only yields physically meaningful results if the input time series does include the $(nts-1)/2$ days before and after each period of interest.

$$\begin{aligned} o(001, x) &= \text{pth percentile}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 001\} \\ &\vdots \\ o(366, x) &= \text{pth percentile}\{i(t, x), i(t+1, x), \dots, i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2)] = 366\} \end{aligned}$$

Parameter

<code>p</code>	INTEGER	Percentile number in 1, ..., 99
<code>nts</code>	INTEGER	Number of time steps

Environment

<code>CDO_PCTL_NBINS</code>	Sets the number of histogram bins. The default number is 100.
-----------------------------	---

Example

Assume the input data provide a continuous time series of daily measurements. To compute the running multi-year daily 90th percentile over all input time steps for a running window of five days use:

```
cdo ydrunmin,5 ifile minfile
cdo ydrunmax,5 ifile maxfile
cdo ydrunpctl,90,5 ifile minfile maxfile ofile
```

Or shorter using operator piping:

```
cdo ydrunpctl,90,5 ifile -ydrunmin ifile -ydrunmax ifile ofile
```

2.9. Regression

This sections contains modules for linear regression of time series.

Here is a short overview of all operators in this section:

regres	Regression
detrend	Detrend
trend	Trend
subtrend	Subtract trend

2.9.1. REGRES - Regression

Synopsis

```
regres ifile ofile
```

Description

The values of the input file `ifile` are assumed to be distributed as $N(a + bt, \sigma^2)$ with unknown a , b and σ^2 . This operator estimates the parameter b . For every field element x only those time steps t belong to the sample $S(x)$, which have $i(t, x) \neq \text{miss}$. It is

$$o(1, x) = \frac{\sum_{t \in S(x)} \left(i(t, x) - \frac{1}{\#S(x)} \sum_{t' \in S(x)} i(t', x) \right) \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)}{\sum_{t \in S(x)} \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)^2}$$

2.9.2. DETREND - Detrend time series

Synopsis

```
detrend ifile ofile
```

Description

Every time series in `ifile` is linearly detrended. For every field element x only those time steps t belong to the sample $S(x)$, which have $i(t, x) \neq \text{miss}$. With

$$a(x) = \frac{1}{\#S(x)} \sum_{t \in S(x)} i(t, x) - b(x) \left(\frac{1}{\#S(x)} \sum_{t \in S(x)} t \right)$$

and

$$b(x) = \frac{\sum_{t \in S(x)} \left(i(t, x) - \frac{1}{\#S(x)} \sum_{t' \in S(x)} i(t', x) \right) \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)}{\sum_{t \in S(x)} \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)^2}$$

it is

$$o(t, x) = i(t, x) - (a(x) + b(x)t)$$

Note

This operator has to keep the fields of all time steps concurrently in the memory. If not enough memory is available use the operators [trend](#) and [subtrend](#).

Example

To detrend the data in `ifile` and to store the detrended data in `ofile` use:

```
cdo detrend ifile ofile
```

2.9.3. TREND - Trend of time series

Synopsis

```
trend ifile ofile1 ofile2
```

Description

The values of the input file `ifile` are assumed to be distributed as $N(a + bt, \sigma^2)$ with unknown a , b and σ^2 . This operator estimates the parameter a and b . For every field element x only those time steps t belong to the sample $S(x)$, which have $i(t, x) \neq \text{miss}$. It is

$$o_1(1, x) = \frac{1}{\#S(x)} \sum_{t \in S(x)} i(t, x) - b(x) \left(\frac{1}{\#S(x)} \sum_{t \in S(x)} t \right)$$

and

$$o_2(1, x) = \frac{\sum_{t \in S(x)} \left(i(t, x) - \frac{1}{\#S(x)} \sum_{t' \in S(x)} i(t', x) \right) \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)}{\sum_{t \in S(x)} \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)^2}$$

Thus the estimation for a is stored in `ofile1` and that for b is stored in `ofile2`. To subtract the trend from the data see operator [subtrend](#).

2.9.4. SUBTREND - Subtract a trend

Synopsis

```
subtrend ifile1 ifile2 ifile3 ofile
```

Description

This operator is for subtracting a trend computed by the operator [trend](#). It is

$$o(t, x) = i_1(t, x) - (i_2(1, x) + i_3(1, x) \cdot t)$$

where t is the time steps.

Example

The typical call for detrending the data in `ifile` and storing the detrended data in `ofile` is:

```
cdo trend ifile afile bfile
cdo subtrend ifile afile bfile ofile
```

The result is identical to a call of the operator [detrend](#):

```
cdo detrend ifile ofile
```


2.10. Interpolation

This section contains modules to interpolate datasets. There are several operators to interpolate horizontal fields to a new grid. Some of those operators can handle only 2D fields on a regular rectangular grid. Vertical interpolation of 3D variables is possible from hybrid model levels to height or pressure levels. Interpolation in time is possible between time steps and years.

Here is a short overview of all operators in this section:

remapbil	Bilinear interpolation
remapbic	Bicubic interpolation
remapcon	Conservative remapping
remapdis	Distance-weighted average remapping
genbil	Generate bilinear interpolation weights
genbic	Generate bicubic interpolation weights
gencon	Generate conservative interpolation weights
gendis	Generate distance-weighted average remap weights
remap	SCRIP grid remapping
interpolate	PINGO grid interpolation
intgridbil	Bilinear grid interpolation
remapeta	Remap vertical hybrid level
ml2pl	Model to pressure level interpolation
ml2hl	Model to height level interpolation
intlevel	Linear level interpolation
inttime	Time interpolation
intntime	Time interpolation
intyear	Year interpolation

2.10.1. REMAPGRID - SCRIP grid interpolation

Synopsis

```
<operator>,grid ifile ofile
```

Description

This module contains operators to interpolate all input fields to a new grid. Each operator uses a different remapping method. The interpolation is based on a special SCRIP library version. For a detailed description of the remapping methods see [\[SCRIP\]](#).

Operators

remapbil	Bilinear interpolation Performs a bilinear interpolation on all input fields. This interpolation method only works on rectangular grids.
remapbic	Bicubic interpolation Performs a bicubic interpolation on all input fields. This interpolation method only works on rectangular grids.
remapcon	Conservative remapping Performs a first order conservative remapping on all input fields.
remapdis	Distance-weighted average remapping Performs a distance-weighted average remapping of the four nearest neighbor values on all input fields.

Parameter

<i>grid</i>	STRING	Target grid description file or name
-------------	--------	--------------------------------------

Environment

NORMALIZE_OPT	This variable is used to choose the normalization of the conservative remapping. By default NORMALIZE_OPT is set to 'fracarea' and will include the destination area fraction in the output weights; other options are 'none' and 'destarea' (for more information see [SCRIP]).
---------------	---

Note

For this program the author has converted the original Fortran 90 SCRIP software to ANSI C. If there are any problems send a bug report to CDO and not to SCRIP!

Example

Say *ifile* contains fields on a rectangular grid. To remap all fields bilinear to a T42 Gaussian grid type:

```
cdo remapbil,t42grid ifile ofile
```

2.10.2. GENWEIGHTS - Generate SCRIP grid interpolation weights

Synopsis

```
<operator>,grid ifile ofile
```

Description

Grid interpolation can be a very time-consuming process. Especially if the data are on an unstructured or a large grid. In this case the [SCRIP](#) interpolation process can be split into two parts. Firstly the generation of the interpolation weights, which is the most time-consuming part. These interpolation weights can be reused for every remapping process with the operator [remap](#). This method should be used only if all input fields are on the same grid and a possibly mask (missing values) does not change. This module contains operators to generate SCRIP interpolation weights of the first input field. Each operator is using a different interpolation method.

Operators

genbil	Generate bilinear interpolation weights Generates bilinear interpolation weights and writes the result to a file. This interpolation method only works on rectangular grids.
genbic	Generate bicubic interpolation weights Generates bicubic interpolation weights and writes the result to a file. This interpolation method only works on rectangular grids.
gencon	Generate conservative interpolation weights Generates first order conservative interpolation weights and writes the result to a file.
gendis	Generate distance-weighted average remap weights Generates distance-weighted average remapping weights of the four nearest neighbor values and writes the result to a file.

Parameter

<i>grid</i>	STRING	Target grid description file or name
-------------	--------	--------------------------------------

Environment

NORMALIZE_OPT	This variable is used to choose the normalization of the conservative interpolation. By default NORMALIZE_OPT is set to 'fracarea' and will include the destination area fraction in the output weights; other options are 'none' and 'destarea' (for more information see [SCRIP]).
---------------	---

Note

For this program the author has converted the original Fortran 90 SCRIP software to ANSI C. If there are any problems send a bug report to CDO and not to SCRIP!

Example

Say `ifile` contains fields on a rectangular grid. To remap all fields bilinear to a T42 Gaussian grid use:

```
cdo genbil,t42grid ifile remapweights.nc
cdo remap,t42grid,remapweights ifile ofile
```

2.10.3. REMAP - SCRIP grid remapping

Synopsis

```
remap,grid,weights ifile ofile
```

Description

This operator remaps all input fields to a new grid. The remap type and the interpolation weights of one input grid are read from a netCDF file. The netCDF file with the weights should follow the [SCRIP](#) convention. Normally these weights come from a previous call to module [GENWEIGHTS](#) or were created by the original SCRIP package.

Parameter

<i>grid</i>	STRING	Target grid description file or name
<i>weights</i>	STRING	Interpolation weights (SCRIP netCDF file)

Note

For this program the author has converted the original Fortran 90 SCRIP software to ANSI C. If there are any problems send a bug report to CDO and not to SCRIP!

Example

Say `ifile` contains fields on a regular grid. To remap all fields bilinear to a T42 Gaussian grid use:

```
cdo genbil,t42grid ifile remapweights.nc
cdo remap,t42grid,remapweights ifile ofile
```

2.10.4. INTGRID - Grid interpolation

Synopsis

```
<operator>,grid ifile ofile
```

Description

This module contains operators to interpolate all input fields to a new grid. All interpolation methods in this module only work on rectangular grids.

Operators

interpolate PINGO grid interpolation
 This is the grid interpolation from PINGO. The base of the interpolation is an underlying continuous field which is constructed in the following way:
 For two neighboured longitudes x_1 and x_2 and two neighboured latitudes y_1 and y_2 of the input grid every point at longitude x and latitude y with $x_1 \leq x \leq x_2$ and $y_1 \leq y \leq y_2$ is assigned the value

$$a = a_{11} + (a_{21} - a_{11}) \frac{x - x_1}{x_2 - x_1} + (a_{12} - a_{11}) \frac{y - y_1}{y_2 - y_1} + (a_{22} - a_{21} - a_{12} + a_{11}) \frac{(x - x_1)(y - y_1)}{(x_2 - x_1)(y_2 - y_1)}$$

where a_{ij} is the value at longitude x_i and latitude y_j . If one out of the four values a_{11} , a_{12} , a_{21} , a_{22} is the missing value then a is also the missing value. Afterwards the underlying continuous field is expanded by a half mesh width. For a detailed description of this interpolation method see [\[PINGO\]](#).

intgridbil Bilinear grid interpolation
 Performs a bilinear interpolation on all input fields. This implementation is faster than [remapbil](#). The complete target grid have to be inside the source grid. Missing values are not supported yet!

Parameter

grid STRING Target grid description file or name

Example

Say *ifile* contains fields on a rectangular grid. To interpolate all fields bilinear to a T42 Gaussian grid use:

```
cdo intgridbil,t42grid ifile ofile
```

2.10.5. REMAPETA - Remap vertical hybrid level

Synopsis

```
remapeta,vct[,oro] ifile ofile
```

Description

This operator interpolates between different vertical hybrid levels. This include the preparation of consistent data for the free atmosphere. The procedure for the vertical interpolation is based on the HIRLAM scheme and was adapted from [\[INTERA\]](#). The vertical interpolation is based on the vertical integration of the hydrostatic equation with few adjustments. The basic tasks are the following one:

- at first integration of hydrostatic equation
- extrapolation of surface pressure
- Planetary Boundary-Layer (PBL) profile interpolation
- interpolation in free atmosphere
- merging of both profiles
- final surface pressure correction

The vertical interpolation corrects the surface pressure. This is simply a cut-off or an addition of air mass. This mass correction should not influence the geostrophic velocity field in the middle troposphere. Therefore the total mass above a given reference level is conserved. As reference level the geopotential height of the 500 hPa level is used. Near the surface the correction can affect the vertical structure of the PBL. Therefore the interpolation is done using the potential temperature. But in the free atmosphere above a certain n ($n=0.8$ defining the top of the PBL) the interpolation is done linearly. After the interpolation both profiles are merged. With the resulting temperature/pressure correction the hydrostatic equation is integrated again and adjusted to the reference level finding the final surface pressure correction. A more detailed description of the interpolation can be found in [\[INTERA\]](#).

Parameter

<code>vct</code>	STRING	File name of an ASCII dataset with the vertical coordinate table
<code>oro</code>	STRING	File name with the orography (surf. geopotential) of the target dataset (optional)

Note

The code number or variable name of the required parameter have to follow the [\[ECHAM\]](#) convention.

Example

To remap between different hybrid model level data use:

```
cdo remapeta,vct ifile ofile
```

2.10.6. INTVERT - Vertical interpolation

Synopsis

```
ml2pl,plevels ifile ofile
```

```
ml2hl,hlevels ifile ofile
```

Description

Interpolate 3D variables on hybrid model levels to pressure or height levels. The input file should contain the log. surface pressure or the surface pressure. To interpolate the temperature, the orography (surface geopotential) is also needed. The pressure, temperature, and orography are identified by their code numbers. Supported parameter tables are: WMO standard table number 2 and ECMWF local table number 128. Use the alias **ml2plx/ml2hlx** or the environment variable **EXTRAPOLATE** to extrapolate missing values.

Operators

- ml2pl** Model to pressure level interpolation
Interpolates 3D variables on hybrid model levels to pressure levels.
- ml2hl** Model to height level interpolation
Interpolates 3D variables on hybrid model levels to height levels. The procedure is the same as for the operator **mh2pl** except for the pressure levels being calculated from the heights by: $p_{level} = 101325 * \exp(h_{level} / -7000)$

Parameter

<i>plevels</i>	FLOAT	Pressure levels in pascal
<i>hlevels</i>	FLOAT	Height levels in meter (max level: 65535 m)

Environment

EXTRAPOLATE If set to 1 extrapolate missing values.

Example

To interpolate hybrid model level data to pressure levels of 925, 850, 500 and 200 hPa use:

```
cdo ml2pl,92500,85000,50000,20000 ifile ofile
```

2.10.7. INTLEVEL - Linear level interpolation

Synopsis

```
intlevel,levels ifile ofile
```

Description

This operator performs a linear vertical interpolation of non hybrid 3D variables.

Parameter

<i>levels</i>	FLOAT	Target levels
---------------	-------	---------------

Example

To interpolate 3D variables on height levels to a new set of height levels use:

```
cdo intlevel,10,50,100,500,1000 ifile ofile
```


2.10.8. INTTIME - Time interpolation

Synopsis

```
inttime,date,time[,inc] ifile ofile
intntime,n ifile ofile
```

Description

This module performs linear interpolation between time steps.

Operators

inttime	Time interpolation This operator creates a new dataset by linear interpolation between time steps. The user has to define the start date/time with an optional increment.
intntime	Time interpolation This operator performs linear interpolation between time steps. The user has to define the number of time steps from one time step to the next.

Parameter

<i>date</i>	STRING	Start date (format YYYY-MM-DD)
<i>time</i>	STRING	Start time (format hh:mm)
<i>inc</i>	STRING	Optional increment (minutes, hours, days, months, years) [default: 0hour]
<i>n</i>	INTEGER	Number of time steps from one time step to the next

Example

Assumed a 6 hourly dataset starts at 1987-01-01 12:00. To interpolate this time series to a one hourly dataset use:

```
cdo inttime,1987-01-01,12:00,1hour ifile ofile
```

2.10.9. INTYEAR - Year interpolation

Synopsis

```
intyear,years ifile1 ifile2 oprefix
```

Description

This operator performs linear interpolation between two years time step by time step. Appends four digits with the year to `oprefix` to form the output file names.

Parameter

<code>years</code>	INTEGER	Comma separated list of years
--------------------	---------	-------------------------------

Example

Assume there are two monthly mean datasets over a year. The first dataset has 12 time steps for the year 1985 and the second one for the year 1990. To interpolate the years between 1985 and 1990 month by month use:

```
cdo intyear,1986,1987,1988,1989 ifile1 ifile2 year
```

Example result of `'dir year*'` for netCDF datasets:

```
year1986.nc year1987.nc year1988.nc year1989.nc
```

2.11. Transformation

This section contains modules to perform spectral transformations.

Here is a short overview of all operators in this section:

sp2gp	Spectral to gridpoint
sp2gpl	Spectral to gridpoint (linear)
gp2sp	Gridpoint to spectral
gp2spl	Gridpoint to spectral (linear)
sp2sp	Spectral to spectral
spcut	Cut spectral wave number
dv2uv	Divergence and vorticity to U and V wind
dv2uwl	Divergence and vorticity to U and V wind (linear)
uv2dv	U and V wind to divergence and vorticity
uv2dwl	U and V wind to divergence and vorticity (linear)

2.11.1. SPECTRAL - Spectral transformation

Synopsis

```

sp2gp  ifile ofile
sp2gpl ifile ofile
gp2sp  ifile ofile
gp2spl ifile ofile
sp2sp, trunc  ifile ofile
spcut, wnums  ifile ofile

```

Description

This module transforms fields on Gaussian grids to spectral coefficients and vice versa.

Operators

sp2gp	<p>Spectral to gridpoint</p> <p>Convert all fields with spectral coefficients to a regular Gaussian grid. The number of latitudes of the resulting Gaussian grid is calculated from the triangular truncation by: $nlat = NINT((trunc * \boxed{3} + 1.) / 2.)$</p>
sp2gpl	<p>Spectral to gridpoint (linear)</p> <p>Convert all fields with spectral coefficients to a regular Gaussian grid. The number of latitudes of the resulting Gaussian grid is calculated from the triangular truncation by: $nlat = NINT((trunc * \boxed{2} + 1.) / 2.)$</p> <p>Use this operator to convert ERA40 data e.g. from TL159 to N80.</p>
gp2sp	<p>Gridpoint to spectral</p> <p>Convert all Gaussian gridpoint fields to spectral coefficients. The triangular truncation of the resulting spherical harmonics is calculated from the number of latitudes by: $trunc = (nlat * 2 - 1) / \boxed{3}$</p>
gp2spl	<p>Gridpoint to spectral (linear)</p> <p>Convert all Gaussian gridpoint fields to spectral coefficients. The triangular truncation of the resulting spherical harmonics is calculated from the number of latitudes by: $trunc = (nlat * 2 - 1) / \boxed{2}$</p> <p>Use this operator to convert ERA40 data e.g. from N80 to TL159 instead of T106.</p>
sp2sp	<p>Spectral to spectral</p> <p>Change the triangular truncation of all spectral fields. The operator performs downward conversion by cutting the resolution. Upward conversions are achieved by filling in zeros.</p>
spcut	<p>Cut spectral wave number</p> <p>Set the user defined wave numbers to zero.</p>

Parameter

<i>trunc</i>	INTEGER	New spectral resolution
<i>wnums</i>	INTEGER	Comma separated list of wave numbers

Example

To transform spectral coefficients from T106 to N80 Gaussian grid use:

```
cdo sp2gp ifile ofile
```

To transform spectral coefficients from TL159 to N80 Gaussian grid use:

```
cdo sp2gpl ifile ofile
```

2.11.2. WIND - Wind transformation

Synopsis

```
<operator> ifile ofile
```

Description

This module converts relative divergence and vorticity to U and V wind and vice versa.

Operators

- | | |
|---------------|---|
| dv2uv | <p>Divergence and vorticity to U and V wind</p> <p>Calculate U and V wind on a Gaussian grid from spherical harmonic coefficients of relative divergence and vorticity. The divergence and vorticity need to have the names sd and svo or code numbers 155 and 138. The number of latitudes of the resulting Gaussian grid is calculated from the triangular truncation by:</p> $nlat = NINT((trunc * \boxed{3} + 1.) / 2.)$ |
| dv2uvl | <p>Divergence and vorticity to U and V wind (linear)</p> <p>Calculate U and V wind on a Gaussian grid from spherical harmonic coefficients of relative divergence and vorticity. The divergence and vorticity need to have the names sd and svo or code numbers 155 and 138. The number of latitudes of the resulting Gaussian grid is calculated from the triangular truncation by:</p> $nlat = NINT((trunc * \boxed{2} + 1.) / 2.)$ |
| uv2dv | <p>U and V wind to divergence and vorticity</p> <p>Calculate spherical harmonic coefficients of relative divergence and vorticity from U and V wind. The U and V wind need to have the names u and v or the code numbers 131 and 132. The triangular truncation of the resulting spherical harmonics is calculated from the number of latitudes by:</p> $trunc = (nlat * 2 - 1) / \boxed{3}$ |
| uv2dvl | <p>U and V wind to divergence and vorticity (linear)</p> <p>Calculate spherical harmonic coefficients of relative divergence and vorticity from U and V wind. The U and V wind need to have the names u and v or the code numbers 131 and 132. The triangular truncation of the resulting spherical harmonics is calculated from the number of latitudes by:</p> $trunc = (nlat * 2 - 1) / \boxed{2}$ |

Example

Assume a dataset has at least spherical harmonic coefficients of divergence and vorticity. To transform the spectral divergence and vorticity to U and V wind use:

```
cdo dv2uv ifile ofile
```

2.12. Formatted I/O

This section contains modules to read and write ASCII data.

Here is a short overview of all operators in this section:

input	ASCII input
inputsrv	SERVICE ASCII input
inputtext	EXTRA ASCII input
output	ASCII output
outputf	Formatted output
outputint	Integer output
outputsrv	SERVICE ASCII output
outputtext	EXTRA ASCII output

2.12.1. INPUT - Formatted input

Synopsis

`input,grid ofile`

`inputsrv ofile`

`inputtext ofile`

Description

This module reads time series of one 2D variable from standard input. All input fields need to have the same horizontal grid. The format of the input depends on the chosen operator.

Operators

input	ASCII input Reads fields with ASCII numbers from standard input and stores them in <code>ofile</code> . The numbers read are exactly that ones which are written out by output .
inputsrv	SERVICE ASCII input Reads fields with ASCII numbers from standard input and stores them in <code>ofile</code> . Each field should have a header of 8 integers (SERVICE likely). The numbers that are read are exactly that ones which are written out by outputsrv .
inputtext	EXTRA ASCII input Read fields with ASCII numbers from standard input and stores them in <code>ofile</code> . Each field should have header of 4 integers (EXTRA likely). The numbers read are exactly that ones which are written out by outputtext .

Parameter

`grid` `STRING` Grid description file or name

Example

Assume an ASCII dataset contains a field on a global regular grid with 32 longitudes and 16 latitudes (512 elements). To create a GRIB dataset from the ASCII dataset use:

```
cdo -f grb input,r32x16 ofile.grb < my_ascii_data
```

2.12.2. OUTPUT - Formatted output

Synopsis

```
output ifiles
outputf,format,nelem ifiles
outputint ifiles
outputsrv ifiles
outputtext ifiles
```

Description

This module prints all values of all input datasets to standard output. All input fields need to have the same horizontal grid. The format of the output depends on the chosen operator.

Operators

output	ASCII output Prints all values to standard output. Each row has 6 elements with the C-style format "%13.6g".
outputf	Formatted output Prints all values to standard output. The format and number of elements for each row have to be specified by the parameters <i>format</i> and <i>nelem</i> .
outputint	Integer output Prints all values rounded to the nearest integer to standard output.
outputsrv	SERVICE ASCII output Prints all values to standard output. Each field with a header of 8 integers (SERVICE likely).
outputtext	EXTRA ASCII output Prints all values to standard output. Each field with a header of 4 integers (EXTRA likely).

Parameter

<i>format</i>	STRING	C-style format for one element (e.g. %13.6g)
<i>nelem</i>	INTEGER	Number of elements for each row

Example

To print all field elements of a dataset formatted with "%8.4g" and 8 values per line use:

```
cd o outputf,%8.4g,8 ifile
```

Example result of a dataset with one field on 64 grid points:

261.7	262	257.8	252.5	248.8	247.7	246.3	246.1
250.6	252.6	253.9	254.8	252	246.6	249.7	257.9
273.4	266.2	259.8	261.6	257.2	253.4	251	263.7
267.5	267.4	272.2	266.7	259.6	255.2	272.9	277.1
275.3	275.5	276.4	278.4	282	269.6	278.7	279.5
282.3	284.5	280.3	280.3	280	281.5	284.7	283.6
292.9	290.5	293.9	292.6	292.7	292.8	294.1	293.6
293.8	292.6	291.2	292.6	293.2	292.8	291	291.2

2.13. Miscellaneous

This section contains miscellaneous modules which do not fit to the other sections before.

Here is a short overview of all operators in this section:

gridarea	Grid cell area
gridweights	Grid cell weights
gradsdes1	GrADS data descriptor file (version 1 GRIB map)
gradsdes2	GrADS data descriptor file (version 2 GRIB map)
smooth9	9 point smoothing
setrtoc	Set range to constant
setrtoc2	Set range to constant others to constant2
timsort	Sort over the time
const	Create a constant field
random	Create a field with random values
rotuvb	Backward rotation
mastrfu	Mass stream function
histcount	Histogram count
histsum	Histogram sum
histmean	Histogram mean
histfreq	Histogram frequency
wct	Windchill temperature
fdns	Frost days where no snow index per time period
strwin	Strong wind days index per time period
strbre	Strong breeze days index per time period
strgal	Strong gale days index per time period
hurr	Hurricane days index per time period
import_amsr	Import AMSR binary files
import_cmsaf	Import CM-SAF files

2.13.1. GRIDCELL - Grid cell quantities

Synopsis

```
<operator> ifile ofile
```

Description

This module reads the grid cell area of the first grid from the input stream. If the grid cell area is missing it will be computed from the grid description. Depending on the chosen operator the grid cell area or weights are written to the output stream.

Operators

gridarea	Grid cell area Writes the grid cell area to the output stream. If the grid cell area have to be computed it is scaled with the earth radius to square meters.
gridweights	Grid cell weights Writes the grid cell area weights to the output stream.

Environment

PLANET_RADIUS	This variable is used to scale the computed grid cell areas to square meters. By default PLANET_RADIUS is set to an earth radius of 6371000 meter.
---------------	--

2.13.2. GRADSDES - GrADS data descriptor file

Synopsis

`<operator> ifile`

Description

Creates a [GrADS](#) data descriptor file. Supported file formats are GRIB, SERVICE, EXTRA and IEG. For GRIB files the GrADS map file is also generated. For SERVICE and EXTRA files the grid have to be specified with the CDO option '-g <grid>'. This module takes `ifile` in order to create filenames for the descriptor (`ifile.ct1`) and the map (`ifile.gmp`) file. "gradsdes" is an alias for [gradsdes2](#).

Operators

- gradsdes1** GrADS data descriptor file (version 1 GRIB map)
Creates a GrADS data descriptor file. Generated a machine specific version 1 GrADS map file for GRIB datasets.
- gradsdes2** GrADS data descriptor file (version 2 GRIB map)
Creates a GrADS data descriptor file. Generated a machine independent version 2 GrADS map file for GRIB datasets. This map file can be used only with GrADS version 1.8 or newer.

Example

To create a GrADS data descriptor file from a GRIB dataset use:

```
cdo gradsdes2 ifile.grb
```

This will create a descriptor file with the name `ifile.ct1` and the map file `ifile.gmp`. Assumed the input GRIB dataset has 3 variables over 12 time steps on a T21 grid. The contents of the resulting GrADS data description file is approximately:

```
DSET ^ifile.grb
DTYPE GRIB
INDEX ^ifile.gmp
XDEF 64 LINEAR 0.000000 5.625000
YDEF 32 LEVELS -85.761 -80.269 -74.745 -69.213 -63.679 -58.143
              -52.607 -47.070 -41.532 -35.995 -30.458 -24.920
              -19.382 -13.844 -8.307 -2.769 2.769 8.307
              13.844 19.382 24.920 30.458 35.995 41.532
              47.070 52.607 58.143 63.679 69.213 74.745
              80.269 85.761
ZDEF 4 LEVELS 925 850 500 200
TDEF 12 LINEAR 12:00 Z1jan1987 1mo
TITLE ifile.grb T21 grid
OPTIONS yrev
UNDEF -9e+33
VARS 3
geosp 0 129,1,0 surface geopotential (orography) [m^2/s^2]
t      4 130,99,0 temperature [K]
tslm1 0 139,1,0 surface temperature of land [K]
ENDVARS
```

2.13.3. SMOOTH9 - 9 point smoothing

Synopsis

```
smooth9 ifile ofile
```

Description

Performs a 9 point smoothing on all fields with a rectangular grid. The result at each grid point is a weighted average of the grid point plus the 8 surrounding points. The center point receives a weight of 1.0, the points at each side and above and below receive a weight of 0.5, and corner points receive a weight of 0.3. All 9 points are multiplied by their weights and summed, then divided by the total weight to obtain the smoothed value. Any missing data points are not included in the sum; points beyond the grid boundary are considered to be missing. Thus the final result may be the result of an averaging with less than 9 points.

2.13.4. SETRANGE - Set range to constant

Synopsis

```
setrtoc,rmin,rmax,c ifile ofile
```

```
setrtoc2,rmin,rmax,c,c2 ifile ofile
```

Description

This module sets part of a field to a constant value or missing values. Which part of the field is set depends on the chosen operator.

Operators

setrtoc Set range to constant

$$o(t, x) = \begin{cases} c & \text{if } i(t, x) \geq rmin \wedge i(t, x) \leq rmax \\ i(t, x) & \text{if } i(t, x) < rmin \vee i(t, x) > rmax \end{cases}$$

setrtoc2 Set range to constant others to constant2

$$o(t, x) = \begin{cases} c & \text{if } i(t, x) \geq rmin \wedge i(t, x) \leq rmax \\ c2 & \text{if } i(t, x) < rmin \vee i(t, x) > rmax \end{cases}$$

Parameter

<i>rmin</i>	FLOAT	Lower bound
<i>rmax</i>	FLOAT	Upper bound
<i>c</i>	FLOAT	New value - inside range
<i>c2</i>	FLOAT	New value - outside range

2.13.5. TIMSORT - Timsort

Synopsis

```
timsort ifile ofile
```

Description

Sorts the elements in ascending order over all time steps for every field position. After sorting it is:

$$o(t_1, x) \leq o(t_2, x) \quad \forall (t_1 < t_2), x$$

Example

To sort all field elements of a dataset over all time steps use:

```
cdo timsort ifile ofile
```

2.13.6. VARGEN - Generate a field

Synopsis

```
const,const,grid ofile
```

```
random,grid ofile
```

Description

Generates a dataset with one field. The size of the field is specified by the user given grid description. According to the chosen operator all field elements are constant or filled with random numbers.

Operators

const	Create a constant field Creates a constant field. All field elements of the grid have the same value.
random	Create a field with random values Creates a field with rectangularly distributed random numbers in the interval [0,1].

Parameter

<i>const</i>	FLOAT	Constant
<i>grid</i>	STRING	Target grid description file or name

2.13.7. ROTUV - Rotation

Synopsis

```
rotuvb,u,v,... ifile ofile
```

Description

This is a special operator for datasets with wind components on a rotated grid, e.g. data from the regional model REMO. It performs a backward transformation of velocity components U and V from a rotated spherical system to a geographical system.

Parameter

<code>u,v,...</code>	STRING	Pairs of zonal and meridional velocity components (use variable names or code numbers)
----------------------	--------	--

Example

To transform the u and v velocity of a dataset from a rotated spherical system to a geographical system use:

```
cdo rotuvb,u,v ifile ofile
```

2.13.8. MASTRFU - Mass stream function

Synopsis

```
mastrfu ifile ofile
```

Description

This is a special operator for the post processing of the atmospheric general circulation model [ECHAM](#). It computes the mass stream function (code number 272). The input dataset have to be a zonal mean of v-velocity (code number 132) on pressure levels.

Example

To compute the mass stream function from a zonal mean v-velocity dataset use:

```
cdo mastrfu ifile ofile
```

2.13.9. HISTOGRAM - Histogram

Synopsis

```
<operator>,<bounds> ifile ofile
```

Description

This module creates bins for a histogram of the input data. The bins have to be adjacent and have non-overlapping intervals. The user has to define the bounds of the bins. The first value is the lower bound and the second value the upper bound of the first bin. The bounds of the second bin are defined by the second and third value, aso. Only 2-dimensional input fields are allowed. The output file contains one vertical level for each of the bins requested.

Operators

histcount	Histogram count Number of elements in the bin range.
histsum	Histogram sum Sum of elements in the bin range.
histmean	Histogram mean Mean of elements in the bin range.
histfreq	Histogram frequency Frequency of elements in the bin range.

Parameter

<i>bounds</i>	FLOAT	Comma separated list of the bin bounds (-inf and inf valid)
---------------	-------	---

2.13.10. WCT - Windchill temperature

Synopsis

```
wct ifile1 ifile2 ofile
```

Description

Let `ifile1` and `ifile2` be time series of temperature and wind speed records, then a corresponding time series of resulting windchill temperatures is written to `ofile`. The wind chill temperature calculation is only valid for a temperature of $T \leq 33$ °C and a wind speed of $v \geq 1.39$ m/s. Whenever these conditions are not satisfied, a missing value is written to `ofile`. Note that temperature and wind speed records have to be given in units of °C and m/s, respectively.

2.13.11. FDNS - Frost days where no snow index per time period

Synopsis

```
fdns ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily minimum temperatures `TN` and `ifile2` be a corresponding series of daily surface snow amounts. Then counted is the number of days where $TN < 0$ °C and the surface snow amount is less than 1 cm. The temperature `TN` have to be given in units of Kelvin. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

2.13.12. STRWIN - Strong wind days index per time period

Synopsis

```
strwin[,v] ifile ofile
```

Description

Let `ifile` be a time series of daily maximum horizontal wind speeds `VX`, then counted is the number of days where $VX > v$. The horizontal wind speed v is an optional parameter with default $v = 10.5$ m/s. A further output variable is the maximum number of consecutive days with maximum wind speed greater than or equal to v . Note that both `VX` and v have to be given in units of m/s. Also note that the horizontal wind speed is defined as the square root of the sum of squares of the zonal and meridional wind speeds. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Parameter

<code>v</code>	FLOAT	Horizontal wind speed threshold (m/s, default $v = 10.5$ m/s)
----------------	-------	---

2.13.13. STRBRE - Strong breeze days index per time period

Synopsis

```
strbre ifile ofile
```

Description

Let `ifile` be a time series of daily maximum horizontal wind speeds VX , then counted is the number of days where VX is greater than or equal to 10.5 m/s. A further output variable is the maximum number of consecutive days with maximum wind speed greater than or equal to 10.5 m/s. Note that VX is defined as the square root of the sum of squares of the zonal and meridional wind speeds and have to be given in units of m/s. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

2.13.14. STRGAL - Strong gale days index per time period

Synopsis

```
strgal ifile ofile
```

Description

Let `ifile` be a time series of daily maximum horizontal wind speeds VX , then counted is the number of days where VX is greater than or equal to 20.5 m/s. A further output variable is the maximum number of consecutive days with maximum wind speed greater than or equal to 20.5 m/s. Note that VX is defined as the square root of the sum of square of the zonal and meridional wind speeds and have to be given in units of m/s. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

2.13.15. HURR - Hurricane days index per time period

Synopsis

```
hurr ifile ofile
```

Description

Let `ifile` be a time series of daily maximum horizontal wind speeds VX , then counted is the number of days where VX is greater than or equal to 32.5 m/s. A further output variable is the maximum number of consecutive days with maximum wind speed greater than or equal to 32.5 m/s. Note that VX is defined as the square root of the sum of squares of the zonal and meridional wind speeds and have to be given in units of m/s. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

2.13.16. IMPORTAMSR - Import AMSR binary files

Synopsis

```
import_amsr ifile ofile
```

Description

This operator imports gridded binary AMSR (Advanced Microwave Scanning Radiometer) data. The binary data files are available from the AMSR ftp site (<ftp://ftp.ssmi.com/amsr>). Each file consists of twelve (daily) or five (averaged) 0.25 x 0.25 degree grid (1440,720) byte maps. For daily files, six daytime maps in the following order, Time (UTC), Sea Surface Temperature (SST), 10 meter Surface Wind Speed (WSPD), Atmospheric Water Vapor (VAPOR), Cloud Liquid Water (CLOUD), and Rain Rate (RAIN), are followed by six nighttime maps in the same order. Time-Averaged files contain just the geophysical layers in the same order [SST, WSPD, VAPOR, CLOUD, RAIN]. More information to the data is available on the AMSR homepage <http://www.remss.com/amsr>.

Example

To convert monthly binary AMSR files to netCDF use:

```
cdo -f nc amsre_yyyymm5 amsre_yyyymm5.nc
```

2.13.17. IMPORTCMSAF - Import CM-SAF files

Synopsis

```
import_cmsaf ifile ofile
```

Description

This operator imports gridded CM-SAF (Satellite Application Facility on Climate Monitoring) HDF5 files.

Note

This operator is only available if the program was compiled with HDF5 support!

Example

To convert a CM-SAF HDF5 file to netCDF use:

```
cdo -f nc ifile.h5 ofile.nc
```

2.14. Climate indices

This section contains modules to compute the climate indices of daily temperature and precipitation extremes.

Here is a short overview of all operators in this section:

eca_cdd	Consecutive dry days index per time period
eca_cfd	Consecutive frost days index per time period
eca_csu	Consecutive summer days index per time period
eca_cwd	Consecutive wet days index per time period
eca_cwdi	Cold wave duration index wrt mean of reference period
eca_cwfi	Cold-spell days index wrt 10th percentile of reference period
eca_etr	Intra-period extreme temperature range
eca_fd	Frost days index per time period
eca_gsl	Growing season length index
eca_hd	Heating degree days per time period
eca_hwdi	Heat wave duration index wrt mean of reference period
eca_hwfi	Warm spell days index wrt 90th percentile of reference period
eca_id	Ice days index per time period
eca_r10mm	Heavy precipitation days index per time period
eca_r20mm	Very heavy precipitation days index per time period
eca_r75p	Moderate wet days wrt 75th percentile of reference period
eca_r75ptot	Precipitation percent due to R75p days
eca_r90p	Wet days wrt 90th percentile of reference period
eca_r90ptot	Precipitation percent due to R90p days
eca_r95p	Very wet days wrt 95th percentile of reference period
eca_r95ptot	Precipitation percent due to R95p days
eca_r99p	Extremely wet days wrt 99th percentile of reference period
eca_r99ptot	Precipitation percent due to R99p days
eca_rr1	Wet days index per time period
eca_rx1day	Highest one day precipitation amount per time period
eca_rx5day	Highest five-day precipitation amount per time period
eca_sdii	Simple daily intensity index per time period

eca_su	Summer days index per time period
eca_tg10p	Cold days percent wrt 10th percentile of reference period
eca_tg90p	Warm days percent wrt 90th percentile of reference period
eca_tn10p	Cold nights percent wrt 10th percentile of reference period
eca_tn90p	Warm nights percent wrt 90th percentile of reference period
eca_tr	Tropical nights index per time period
eca_tx10p	Very cold days percent wrt 10th percentile of reference period
eca_tx90p	Very warm days percent wrt 90th percentile of reference period

2.14.1. ECACDD - Consecutive dry days index per time period

Synopsis

```
eca_cdd ifile ofile
```

Description

Let `ifile` be a time series of daily precipitation amounts `RR`, then counted is the largest number of consecutive days where `RR` is less than 1 mm. A further output variable is the number of dry periods of more than 5 days. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the largest number of consecutive dry days of a time series of daily precipitation amounts use:

```
cdo eca_cdd rrfile ofile
```

2.14.2. ECACFD - Consecutive frost days index per time period

Synopsis

```
eca_cfd ifile ofile
```

Description

Let `ifile` be a time series of daily minimum temperatures `TN`, then counted is the largest number of consecutive days where $TN < 0$ °C. Note that `TN` have to be given in units of Kelvin. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the largest number of consecutive frost days of a time series of daily minimum temperatures use:

```
cdo eca_cfd tnfile ofile
```

2.14.3. ECACSU - Consecutive summer days index per time period

Synopsis

```
eca_csu[,T] ifile ofile
```

Description

Let `ifile` be a time series of daily maximum temperatures TX, then counted is the largest number of consecutive days where $TX > T$. The number T is an optional parameter with default $T = 25\text{ }^{\circ}\text{C}$. Note that TN have to be given in units of Kelvin, whereas T have to be given in degrees Celsius. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Parameter

<i>T</i>	FLOAT	Temperature threshold (Celsius, default: $T = 25\text{ Celsius}$)
----------	-------	---

Example

To get the largest number of consecutive summer days of a time series of daily minimum temperatures use:

```
cdo eca_csu txfile ofile
```

2.14.4. ECACWD - Consecutive wet days index per time period

Synopsis

```
eca_cwd ifile ofile
```

Description

Let `ifile` be a time series of daily precipitation amounts RR, then counted is the largest number of consecutive days where RR is at least 1 mm. A further output variable is the number of wet periods of more than 5 days. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the largest number of consecutive wet days of a time series of daily precipitation amounts use:

```
cdo eca_cwd rrfile ofile
```

2.14.5. ECACWDI - Cold wave duration index wrt mean of reference period

Synopsis

```
eca_cwdi[,nday[,T]] ifile1 ifile2 ofile
```

Description

Let *ifile1* be a time series of daily minimum temperatures *TN*, and let *ifile2* be the mean *TN*_{norm} of daily minimum temperatures for any period used as reference. Then counted is the number of days where, in intervals of at least *nday* consecutive days, $TN < TN_{norm} - T$. The numbers *nday* and *T* are optional parameters with default *nday* = 6 and *T* = 5 °C. A further output variable is the number of cold waves longer than or equal to *nday* days. Note that both *TN* and *TN*_{norm} have to be given in the same units. The date information of a time step in *ofile* is the date of the last contributing time step in *ifile1*.

Parameter

<i>nday</i>	INTEGER	Number of consecutive days (default: <i>nday</i> = 6)
<i>T</i>	FLOAT	Temperature offset (Celsius, default: <i>T</i> = 5 Celsius)

Example

To compute the cold wave duration index of a time series of daily minimum temperatures use:

```
cdo eca_cwdi tfile tnnormfile ofile
```

2.14.6. ECACWFI - Cold-spell days index wrt 10th percentile of reference period

Synopsis

```
eca_cwfi[,nday] ifile1 ifile2 ofile
```

Description

Let *ifile1* be a time series of daily mean temperatures *TG*, and *ifile2* be the 10th percentile *TG*_{n10} of daily mean temperatures for any period used as reference. Then counted is the number of days where, in intervals of at least *nday* consecutive days, $TG < TG_{n10}$. The number *nday* is an optional parameter with default *nday* = 6. A further output variable is the number of cold-spell periods longer than or equal to *nday* days. Note that both *TG* and *TG*_{n10} have to be given in the same units. The date information of a time step in *ofile* is the date of the last contributing time step in *ifile1*.

Parameter

<i>nday</i>	INTEGER	Number of consecutive days (default: <i>nday</i> = 6)
-------------	---------	---

Example

To compute the number of cold-spell days of a time series of daily mean temperatures use:

```
cdo eca_cwfi tgfile tgn10file ofile
```

2.14.7. ECAETR - Intra-period extreme temperature range

Synopsis

```
eca_etr ifile1 ifile2 ofile
```

Description

Let `ifile1` and `ifile2` be time series of maximum and minimum temperatures TX and TN, respectively. Then the extreme temperature range is the difference of the maximum of TX and the minimum of TN. Note that TX and TN have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time steps in `ifile1` and `ifile2`.

Example

To get the intra-period extreme temperature range for two time series of maximum and minimum temperatures use:

```
cdo eca_etr txfile tnfile ofile
```

2.14.8. ECAFD - Frost days index per time period

Synopsis

```
eca_fd ifile ofile
```

Description

Let `ifile` be a time series of daily minimum temperatures TN, then counted is the number of days where $TN < 0\text{ }^{\circ}\text{C}$. Note that TN have to be given in units of Kelvin. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the number of frost days of a time series of daily minimum temperatures use:

```
cdo eca_fd tnfile ofile
```


2.14.9. ECAGSL - Growing season length index

Synopsis

```
eca_gsl[,nday[,T[,fland]]] ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily mean temperatures `TG`, and `ifile2` be a land-water mask. Then counted are the number of days between the first occurrence of at least `nday` consecutive days with `TG > T` and the first occurrence after 1 July of at least `nday` consecutive days with `TG < T`. The numbers `nday` and `T` are optional parameter with default `nday = 6` and `T = 5 °C`. The number `fland` is an optional parameter with default value `fland = 0.5` and denotes the fraction of a grid point that have to be covered by land in order to be included in the calculation. A further output variable is the start day of year of the growing season. Note that `TG` have to be given in units of Kelvin, whereas `T` have to be given in degrees Celsius. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Parameter

<code>nday</code>	INTEGER	Number of consecutive days (default: <code>nday = 6</code>)
<code>T</code>	FLOAT	Temperature threshold (degree Celsius, default: <code>T = 5 Celsius</code>)
<code>fland</code>	FLOAT	Land fraction threshold (default: <code>fland = 0.5</code>)

Example

To get the growing season length of a time series of daily mean temperatures use:

```
cdo eca_gsl tgfile maskfile ofile
```

2.14.10. ECAHD - Heating degree days per time period

Synopsis

```
eca_hd[,T1[,T2]] ifile ofile
```

Description

Let `ifile` be a time series of daily mean temperatures `TG`, then the heating degree days are defined as the sum of $T1 - TG$, where only values $TG < T2$ are considered. If `T1` and `T2` are omitted, a temperature of 17 °C is used for both parameters. If only `T1` is given, `T2` is set to `T1`. Note that `TG` have to be given in units of kelvin, whereas `T1` and `T2` have to be given in degrees Celsius. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Parameter

<code>T1</code>	FLOAT	Temperature limit (Celsius, default: $T1 = 17$ Celsius)
<code>T2</code>	FLOAT	Temperature limit (Celsius, default: $T2 = T1$)

Example

To compute the heating degree days of a time series of daily mean temperatures use:

```
cdo eca_hd tgfile ofile
```

2.14.11. ECAHWDI - Heat wave duration index wrt mean of reference period

Synopsis

```
eca_hwdi[,nday[,T]] ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily maximum temperatures `TX`, and let `ifile2` be the mean `TXnorm` of daily maximum temperatures for any period used as reference. Then counted is the number of days where, in intervals of at least `nday` consecutive days, $TX > TXnorm + T$. The numbers `nday` and `T` are optional parameters with default `nday = 6` and $T = 5$ °C. A further output variable is the number of heat waves longer than or equal to `nday` days. Note that both `TX` and `TXnorm` have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Parameter

<code>nday</code>	INTEGER	Number of consecutive days (default: <code>nday = 6</code>)
<code>T</code>	FLOAT	Temperature offset (Celsius, default: $T = 5$ Celsius)

Example

To compute the heat wave duration index of a time series of daily maximum temperatures use:

```
cdo eca_hwdi txfile txnormfile ofile
```

2.14.12. ECAHWFI - Warm spell days index wrt 90th percentile of reference period

Synopsis

```
eca_hwfi[,nday] ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily mean temperatures `TG`, and `ifile2` be the 90th percentile `TGn90` of daily mean temperatures for any period used as reference. Then counted is the number of days where, in intervals of at least `nday` consecutive days, $TG > TGn90$. The number `nday` is an optional parameter with default `nday = 6`. A further output variable is the number of warm-spell periods longer than or equal to `nday` days. Note that both `TG` and `TGn90` have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Parameter

`nday` INTEGER Number of consecutive days (default: `nday = 6`)

Example

To compute the number of warm-spell days of a time series of daily mean temperatures use:

```
cdo eca_hwfi tgfile tgn90file ofile
```

2.14.13. ECAID - Ice days index per time period

Synopsis

```
eca_id ifile ofile
```

Description

Let `ifile` be a time series of daily maximum temperatures `TX`, then counted is the number of days where $TX < 0\text{ }^{\circ}\text{C}$. Note that `TX` have to be given in units of Kelvin. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the number of ice days of a time series of daily maximum temperatures use:

```
cdo eca_id txfile ofile
```

2.14.14. ECAR10MM - Heavy precipitation days index per time period

Synopsis

```
eca_r10mm ifile ofile
```

Description

Let `ifile` be a time series of daily precipitation amounts `RR`, then counted is the number of days where `RR` is at least 10 mm. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the number of days with precipitation greater than 10 mm for a time series of daily precipitation amounts use:

```
cdo eca_r10mm rrfile ofile
```

2.14.15. ECAR20MM - Very heavy precipitation days index per time period

Synopsis

```
eca_r20mm ifile ofile
```

Description

Let `ifile` be a time series of daily precipitation amounts `RR`, then counted is the number of days where `RR` is at least 20 mm. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the number of days with precipitation greater than 20 mm for a time series of daily precipitation amounts use:

```
cdo eca_r20mm rrfile ofile
```

2.14.16. ECAR75P - Moderate wet days wrt 75th percentile of reference period

Synopsis

```
eca_r75p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily precipitation amounts `RR`, and `ifile2` be the 75th percentile `RRn75` of daily precipitation amounts at wet days for any period used as reference. Then calculated is the percentage of wet days with $RR > RRn75$. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of wet days where the daily precipitation amount is greater than the 75th percentile of the daily precipitation amount at wet days for a given reference period use:

```
cdo eca_r75p rrfile rrn75file ofile
```

2.14.17. ECAR75PTOT - Precipitation percent due to R75p days

Synopsis

```
eca_r75ptot ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily precipitation amounts `RR`, and `ifile2` be the 75th percentile `RRn75` of daily precipitation amounts at wet days for any period used as reference. Then calculated is the ratio of the precipitation sum at wet days with $RR > RRn75$ to the total precipitation sum. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

2.14.18. ECAR90P - Wet days wrt 90th percentile of reference period

Synopsis

```
eca_r90p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily precipitation amounts `RR`, and `ifile2` be the 90th percentile `RRn90` of daily precipitation amounts at wet days for any period used as reference. Then calculated is the percentage of wet days with $RR > RRn90$. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of wet days where the daily precipitation amount is greater than the 90th percentile of the daily precipitation amount at wet days for a given reference period use:

```
cdo eca_r90p rfile rrn90file ofile
```

2.14.19. ECAR90PTOT - Precipitation percent due to R90p days

Synopsis

```
eca_r90ptot ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily precipitation amounts `RR`, and `ifile2` be the 90th percentile `RRn90` of daily precipitation amounts at wet days for any period used as reference. Then calculated is the ratio of the precipitation sum at wet days with $RR > RRn90$ to the total precipitation sum. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

2.14.20. ECAR95P - Very wet days wrt 95th percentile of reference period

Synopsis

```
eca_r95p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily precipitation amounts `RR`, and `ifile2` be the 95th percentile `RRn95` of daily precipitation amounts at wet days for any period used as reference. Then calculated is the percentage of wet days with $RR > RRn95$. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of wet days where the daily precipitation amount is greater than the 95th percentile of the daily precipitation amount at wet days for a given reference period use:

```
cdo eca_r95p rrfile rrn95file ofile
```

2.14.21. ECAR95PTOT - Precipitation percent due to R95p days

Synopsis

```
eca_r95ptot ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily precipitation amounts `RR`, and `ifile2` be the 95th percentile `RRn95` of daily precipitation amounts at wet days for any period used as reference. Then calculated is the ratio of the precipitation sum at wet days with $RR > RRn95$ to the total precipitation sum. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

2.14.22. ECAR99P - Extremely wet days wrt 99th percentile of reference period

Synopsis

```
eca_r99p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily precipitation amounts `RR`, and `ifile2` be the 99th percentile `RRn99` of daily precipitation amounts at wet days for any period used as reference. Then calculated is the percentage of wet days with $RR > RRn99$. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of wet days where the daily precipitation amount is greater than the 99th percentile of the daily precipitation amount at wet days for a given reference period use:

```
cdo eca_r99p rfile rrn99file ofile
```

2.14.23. ECAR99PTOT - Precipitation percent due to R99p days

Synopsis

```
eca_r99ptot ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily precipitation amounts `RR`, and `ifile2` be the 99th percentile `RRn99` of daily precipitation amounts at wet days for any period used as reference. Then calculated is the ratio of the precipitation sum at wet days with $RR > RRn99$ to the total precipitation sum. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

2.14.24. ECARR1 - Wet days index per time period

Synopsis

```
eca_rr1 ifile ofile
```

Description

Let `ifile` be a time series of daily precipitation amounts `RR`, then counted is the number of days where `RR` is at least 1 mm. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the number of wet days of a time series of daily precipitation amounts use:

```
cdo eca_rr1 rrfile ofile
```

2.14.25. ECARX1DAY - Highest one day precipitation amount per time period

Synopsis

```
eca_rx1day[,mode] ifile ofile
```

Description

Let `ifile` be a time series of daily precipitation amounts `RR`, then the maximum of `RR` is written to `ofile`. If the optional parameter `mode` is set to 'm', then maximum daily precipitation amounts are determined for each month. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Parameter

<i>mode</i>	STRING	Operation mode (optional). If <code>mode = 'm'</code> then maximum daily precipitation amounts are determined for each month
-------------	--------	--

Example

To get the maximum of a time series of daily precipitation amounts use:

```
cdo eca_rx1day rrfile ofile
```

If you are interested in the maximum daily precipitation for each month, use:

```
cdo eca_rx1day,m rrfile ofile
```

Apart from metadata information, both operations yield the same as:

```
cdo timmax rrfile ofile
cdo monmax rrfile ofile
```

2.14.26. ECARX5DAY - Highest five-day precipitation amount per time period

Synopsis

```
eca_rx5day[,x] ifile ofile
```

Description

Let `ifile` be a time series of 5-day precipitation totals `RR`, then the maximum of `RR` is written to `ofile`. A further output variable is the number of 5 day period with precipitation totals greater than `x` mm, where `x` is an optional parameter with default `x = 50` mm. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Parameter

<code>x</code>	FLOAT	Precipitation threshold (mm, default: <code>x = 50</code> mm)
----------------	-------	---

Example

To get the maximum of a time series of 5-day precipitation totals use:

```
cdo eca_rx5day rrfile ofile
```

Apart from metadata information, the above operation yields the same as:

```
cdo timmax rrfile ofile
```

2.14.27. ECASDII - Simple daily intensity index per time period

Synopsis

```
eca_sdii ifile ofile
```

Description

Let `ifile` be a time series of daily precipitation amounts `RR`, then the mean precipitation amount at wet days (`RR > 1` mm) is written to `ofile`. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Example

To get the daily intensity index of a time series of daily precipitation amounts use:

```
cdo eca_sdii rrfile ofile
```

2.14.28. ECASU - Summer days index per time period

Synopsis

```
eca_su[,T] ifile ofile
```

Description

Let `ifile` be a time series of daily maximum temperatures `TX`, then counted is the number of days where $TX > T$. The number `T` is an optional parameter with default $T = 25$ °C. Note that `TX` have to be given in units of Kelvin, whereas `T` have to be given in degrees Celsius. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Parameter

<code>T</code>	FLOAT	Temperature threshold (degree Celsius, default: $T = 25$ Celsius)
----------------	-------	---

Example

To get the number of summer days of a time series of daily maximum temperatures use:

```
cdo eca-su txfile ofile
```

2.14.29. ECATG10P - Cold days percent wrt 10th percentile of reference period

Synopsis

```
eca_tg10p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily mean temperatures TG, and `ifile2` be the 10th percentile TGn10 of daily mean temperatures for any period used as reference. Then calculated is the percentage of time where $TG < TGn10$. Note that both TG and TGn10 have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of time where the daily mean temperature is less than the 10th percentile of the daily mean temperature for a given reference period use:

```
cdo eca_tg10p tgfile tgn10file ofile
```

2.14.30. ECATG90P - Warm days percent wrt 90th percentile of reference period

Synopsis

```
eca_tg90p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily mean temperatures TG, and `ifile2` be the 90th percentile TGn90 of daily mean temperatures for any period used as reference. Then calculated is the percentage of time where $TG > TGn90$. Note that both TG and TGn90 have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of time where the daily mean temperature is greater than the 90th percentile of the daily mean temperature for a given reference period use:

```
cdo eca_tg90p tgfile tgn90file ofile
```

2.14.31. ECATN10P - Cold nights percent wrt 10th percentile of reference period

Synopsis

```
eca_tn10p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily minimum temperatures `TN`, and `ifile2` be the 10th percentile `TNn10` of daily minimum temperatures for any period used as reference. Then calculated is the percentage of time where $TN < TNn10$. Note that both `TN` and `TNn10` have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of time where the daily minimum temperature is less than the 10th percentile of the daily minimum temperature for a given reference period use:

```
cdo eca_tn10p tnfile tnn10file ofile
```

2.14.32. ECATN90P - Warm nights percent wrt 90th percentile of reference period

Synopsis

```
eca_tn90p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily minimum temperatures `TN`, and `ifile2` be the 90th percentile `TNn90` of daily minimum temperatures for any period used as reference. Then calculated is the percentage of time where $TN > TNn90$. Note that both `TN` and `TNn90` have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of time where the daily minimum temperature is greater than the 90th percentile of the daily minimum temperature for a given reference period use:

```
cdo eca_tn90p tnfile tnn90file ofile
```

2.14.33. ECATR - Tropical nights index per time period

Synopsis

```
eca_tr[,T] ifile ofile
```

Description

Let `ifile` be a time series of daily minimum temperatures `TN`, then counted is the number of days where $TN > T$. The number `T` is an optional parameter with default $T = 20$ °C. Note that `TN` have to be given in units of Kelvin, whereas `T` have to be given in degrees Celsius. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile`.

Parameter

<code>T</code>	FLOAT	Temperature threshold (Celsius, default: $T = 20$ Celsius)
----------------	-------	---

Example

To get the number of tropical nights of a time series of daily minimum temperatures use:

```
cdo eca_tr tnfile ofile
```

2.14.34. ECATX10P - Very cold days percent wrt 10th percentile of reference period

Synopsis

```
eca_tx10p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily maximum temperatures `TX`, and `ifile2` be the 10th percentile `TNx10` of daily maximum temperatures for any period used as reference. Then calculated is the percentage of time where $TX < TX_{n10}$. Note that both `TX` and `TNx10` have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of time where the daily maximum temperature is less than the 10th percentile of the daily maximum temperature for a given reference period use:

```
cdo eca_tx10p txfile txn10file ofile
```

2.14.35. ECATX90P - Very warm days percent wrt 90th percentile of reference period

Synopsis

```
eca_tx90p ifile1 ifile2 ofile
```

Description

Let `ifile1` be a time series of daily maximum temperatures TX, and `ifile2` be the 90th percentile TX_{n90} of daily maximum temperatures for any period used as reference. Then calculated is the percentage of time where TX > TX_{n90}. Note that both TX and TX_{n90} have to be given in the same units. The date information of a time step in `ofile` is the date of the last contributing time step in `ifile1`.

Example

To compute the percentage of time where the daily maximum temperature is greater than the 90th percentile of the daily maximum temperature for a given reference period use:

```
cdo eca_tx90p txfile txn90file ofile
```

Bibliography

[CDI]

[Climate Data Interface](#), from the [Max Planck Institute for Meteorologie](#)

[ECHAM]

The atmospheric general circulation model [ECHAM5](#), from the [Max Planck Institute for Meteorologie](#)

[GrADS]

[Grid Analysis and Display System](#), from the Center for Ocean-Land-Atmosphere Studies ([COLA](#))

[GRIB]

[GRIB version 1](#), from the World Meteorological Organisation ([WMO](#))

[HDF5]

[HDF version 5](#), from the HDF Group

[INTERA]

[INTERA Software Package](#), from the [Max Planck Institute for Meteorologie](#)

[MPIOM]

[Ocean and sea ice model](#), from the [Max Planck Institute for Meteorologie](#)

[netCDF]

[NetCDF Software Package](#), from the [UNIDATA](#) Program Center of the University Corporation for Atmospheric Research

[PINGO]

The [PINGO](#) package, from the [Model & Data group](#) at the [Max Planck Institute for Meteorologie](#)

[REMO]

[Regional Model](#), from the [Max Planck Institute for Meteorologie](#)

[SCRIP]

[SCRIP Software Package](#), from the Los Alamos National Laboratory

[gzip]

[Gzip compression software](#), developed at University of New Mexico.

A. Hints for PINGO user

Some **CDO** operators have the same name as in PINGO but the meaning is different. The following table gives an overview of those operators.

Operator name	CDO	PINGO
min	Minimum of two fields	Time minimum
max	Maximum of two fields	Time maximum
daymean	Daily mean	Multi-year daily mean
daymin	Daily minimum	Multi-year daily minimum
daymax	Daily maximum	Multi-year daily maximum
monmean	Monthly mean	Multi-year monthly mean
monmin	Monthly minimum	Multi-year monthly minimum
monmax	Monthly maximum	Multi-year monthly maximum
seasmean	Seasonally mean	Multi-year seasonally mean

There are also some **CDO** operators with the same functionality as in PINGO but the name is different. The following table gives an overview of those operators.

	CDO	PINGO
Maximum of two fields	max	max2
Minimum of two fields	min	min2
Field mean, min, max	fldmean, fldmin, fldmax	meanr minr, maxr
Time mean, min, max	timmean, timmin, timmax	mean, min, max
Daily mean, min, max	daymean, daymin, daymax	daymeans, daymins, daymaxs
Monthly mean, min, max	monmean, monmin, monmax	monmeans, monmins, monmaxs
Yearly mean, min, max	yearmean, yearmin, yearmax	yearmeans, yearmins, yearmaxs
Running mean	runmean	runmeans
Seasonally mean	seasmean	seasmeans
Multi-year daily mean	ydaymean	daymean
Multi-year monthly mean	ymonmean	monmean
Multi-year seasonally mean	yseasmean	seasmean

B. Grid description examples

B.1. Example of a curvilinear grid description

Here is an example for the **CDO** description of a curvilinear grid. `xvals/yvals` describes the position of the 6x5 quadrilateral grid cells. The first 4 values of `xbounds/ybounds` are the corners of the first grid cell.

gridtype	:	curvilinear													
gridsize	:	30													
xsize	:	6													
ysize	:	5													
xvals	:	-21	-11	0	11	21	30	-25	-13	0	13				
		25	36	-31	-16	0	16	31	43	-38	-21				
		0	21	38	52	-51	-30	0	30	51	64				
xbounds	:	-23	-14	-17	-28		-14	-5	-6	-17		-5	5	6	-6
		5	14	17	6		14	23	28	17		23	32	38	28
		-28	-17	-21	-34		-17	-6	-7	-21		-6	6	7	-7
		6	17	21	7		17	28	34	21		28	38	44	34
		-34	-21	-27	-41		-21	-7	-9	-27		-7	7	9	-9
		7	21	27	9		21	34	41	27		34	44	52	41
		-41	-27	-35	-51		-27	-9	-13	-35		-9	9	13	-13
		9	27	35	13		27	41	51	35		41	52	63	51
		-51	-35	-51	-67		-35	-13	-21	-51		-13	13	21	-21
		13	35	51	21		35	51	67	51		51	63	77	67
yvals	:	29	32	32	32	29	26	39	42	42	42	42			
		39	35	48	51	52	51	48	43	57	61	61			
		62	61	57	51	65	70	72	70	65	58	58			
ybounds	:	23	26	36	32		26	27	37	36		27	27	37	37
		27	26	36	37		26	23	32	36		23	19	28	32
		32	36	45	41		36	37	47	45		37	37	47	47
		37	36	45	47		36	32	41	45		32	28	36	41
		41	45	55	50		45	47	57	55		47	47	57	57
		47	45	55	57		45	41	50	55		41	36	44	50
		50	55	64	58		55	57	67	64		57	57	67	67
		57	55	64	67		55	50	58	64		50	44	51	58
		58	64	72	64		64	67	77	72		67	67	77	77
		67	64	72	77		64	58	64	72		58	51	56	64




Figure B.1.: Orthographic and Robinson projection of the curvilinear grid

B.2. Example description for unstructured grid cells

Here is an example of the **CDO** description for unstructured grid cells. xvals/yvals describes the position of 30 independent hexagonal grid cells. The first 6 values of xbounds/ybounds are the corners of the first grid cell.

```

gridtype : cell
gridsize : 30
nvertex  : 6
xvals    : -36  36   0  -18  18  108  72  54  90  180
           144 126 162 -108 -144 -162 -126 -72 -90 -54
           0   72  36  144 108 -144 180 -72 -108 -36
xbounds   : 339   0   0  288 288 309   21  51  72  72   0   0
           0   16  21   0  339 344   340   0  -0  344 324 324
           20  36  36  16   0   0   93 123 144 144 72 72
           72  88  93  72  51  56   52  72  72  56  36  36
           92 108 108  88  72  72   165 195 216 216 144 144
           144 160 165 144 123 128   124 144 144 128 108 108
           164 180 180 160 144 144   237 267 288 288 216 216
           216 232 237 216 195 200   196 216 216 200 180 180
           236 252 252 232 216 216   288 304 309 288 267 272
           268 288 288 272 252 252   308 324 324 304 288 288
           345 324 324  36  36  15    36  36 108 108  87  57
           20  15  36  57  52  36   108 108 180 180 159 129
           92  87 108 129 124 108   180 180 252 252 231 201
           164 159 180 201 196 180   252 252 324 324 303 273
           236 231 252 273 268 252   308 303 324 345 340 324
yvals     :  58  58  32   0   0  58  32   0   0  58
           32   0   0  58  32   0   0  32   0   0
           -58 -58 -32 -58 -32 -58 -32 -58 -32 -32
ybounds   :  41  53  71  71  53  41   41  41  53  71  71  53
           11  19  41  53  41  19   -19 -7  11  19  7 -11
           -19 -11  7  19  11 -7    41  41  53  71  71  53
           11  19  41  53  41  19   -19 -7  11  19  7 -11
           -19 -11  7  19  11 -7    41  41  53  71  71  53
           11  19  41  53  41  19   -19 -7  11  19  7 -11
           -19 -11  7  19  11 -7    11  19  41  53  41  19
           -19 -7  11  19  7 -11   -19 -11  7  19  11 -7
           -41 -53 -71 -71 -53 -41   -53 -71 -71 -53 -41 -41
           -19 -41 -53 -41 -19 -11   -53 -71 -71 -53 -41 -41
           -19 -41 -53 -41 -19 -11   -53 -71 -71 -53 -41 -41
           -19 -41 -53 -41 -19 -11   -53 -71 -71 -53 -41 -41
           -19 -41 -53 -41 -19 -11   -19 -41 -53 -41 -19 -11

```




Figure B.2.: Orthographic and Robinson projection of the unstructured grid cells

Operator index

A

abs	57
acos	57
add	59
addc	58
asin	57
atan	57
atan2	59

C

cat	25
chcode	46
chlevel	46
chlevelc	46
chlevelv	46
chname	46
const	125
copy	25
cos	57

D

dayavg	84
daymax	84
daymean	84
daymin	84
daypctl	85
daystd	84
daysum	84
dayvar	84
delcode	31
delname	31
detrend	103
diff	20
diffv	20
div	59
divc	58
divdpm	62
divdpy	62
dv2uv	117
dv2uyl	117

E

eca_cdd	133
eca_cfd	133
eca_csu	134
eca_cwd	134
eca_cwdi	135
eca_cwfi	135
eca_etr	136
eca_fd	136

eca_gsl	137
eca_hd	138
eca_hwdi	138
eca_hwfi	139
eca_id	139
eca_r10mm	140
eca_r20mm	140
eca_r75p	141
eca_r75ptot	141
eca_r90p	142
eca_r90ptot	142
eca_r95p	143
eca_r95ptot	143
eca_r99p	144
eca_r99ptot	144
eca_rr1	145
eca_rx1day	145
eca_rx5day	146
eca_sdii	146
eca_su	146
eca_tg10p	148
eca_tg90p	148
eca_tn10p	149
eca_tn90p	149
eca_tr	150
eca_tx10p	150
eca_tx90p	151
enlarge	53
ensavg	67
ensmax	67
ensmean	67
ensmin	67
enspctl	67
ensstd	67
enssum	67
ensvar	67
eq	40
eqc	41
exp	57
expr	56
exprf	56

F

fdns	128
fldavg	69
fldmax	69
fldmean	69
fldmin	69
fldpctl	69
fldstd	69

fldsum	69
fldvar	69

G

ge	40
gec	41
genbic	107
genbil	107
gencon	107
gendis	107
gp2sp	116
gp2spl	116
gradsdes1	123
gradsdes2	123
gridarea	122
griddes	23
gridweights	122
gt	40
gtc	41

H

histcount	127
histfreq	127
histmean	127
histsum	127
houravg	82
hourmax	82
hourmean	82
hourmin	82
hourpctl	83
hourstd	82
hoursum	82
hourvar	82
hurr	129

I

ifnotthen	37
ifnotthenc	38
ifthen	37
ifthenc	38
ifthenelse	37
import_amsr	130
import_cmsaf	130
info	18
infov	18
input	119
inputext	119
inputsrv	119
int	57
interpolate	109
intgridbil	109
intlevel	112
intntime	113
inttime	113
intyear	114
invertlat	49
invertlev	49

L

le	40
lec	41
ln	57
log10	57
lt	40
ltc	41

M

map	18
maskindexbox	51
masklonlatbox	51
maskregion	50
mastrfu	126
max	59
meravg	73
merge	26
mergetime	26
mermax	73
mermean	73
mermin	73
merpctl	73
merstd	73
mersum	73
mervar	73
min	59
ml2hl	111
ml2pl	111
monadd	60
monavg	86
monddiv	60
monmax	86
monmean	86
monmin	86
monmul	60
monpctl	87
monstd	86
monsub	60
monsum	86
monvar	86
mul	59
mulc	58
muldpm	62
muldpy	62

N

ndate	21
ne	40
nec	41
nint	57
nlevel	21
nmon	21
npar	21
ntime	21
nyear	21

O

output	120
outputext	120

outputf	120
outputint	120
outputsrv	120

P

pardes	23
pow	57

R

random	125
regres	103
remap	108
remapbic	106
remapbil	106
remapcon	106
remapdis	106
remapeta	110
replace	25
rotuvb	126
runavg	78
runmax	78
runmean	78
runmin	78
runpctl	79
runstd	78
runsum	78
runvar	78

S

seasavg	90
seasmax	90
seasmean	90
seasmin	90
seaspctl	91
seasstd	90
seassum	90
seasvar	90
selcode	31
seldate	33
selday	33
selgrid	31
selgridname	31
selhour	33
selindexbox	35
sellevel	31
sellevidx	31
sellonlatbox	35
selltype	31
selmon	33
selname	31
selseas	33
selsmon	33
selstdname	31
seltabnum	31
selttime	33
seltimestep	33
selyear	33
selzaxis	31

selzaxisname	31
setcalendar	44
setcindexbox	52
setclonlatbox	52
setcode	43
setctomiss	54
setdate	44
setday	44
setgatt	48
setgatts	48
setgrid	47
setgridtype	47
setlevel	43
setltype	43
setmisstoc	54
setmissval	54
setmon	44
setname	43
setpartab	43
setreftime	44
setrtoc	124
setrtoc2	124
setrtomiss	54
settaxis	44
settime	44
setunits	44
setyear	44
setzaxis	47
shifttime	44
showcode	22
showdate	22
showformat	22
showlevel	22
showltype	22
showmon	22
shownname	22
showstdname	22
showtime	22
showyear	22
sin	57
sinfo	19
sinfop	19
sinfov	19
smooth9	124
sp2gp	116
sp2gpl	116
sp2sp	116
spcut	116
splitcode	27
splitday	28
splitgrid	27
splithour	28
splitlevel	27
splitmon	28
splitname	27
splitseas	28
splitsel	29
splityear	28

splitzaxis	27
sqr	57
sqrt	57
strbre	129
strgal	129
strwin	128
sub	59
subc	58
subtrend	104

T

tan	57
timavg	80
timmax	80
timmean	80
timmin	80
timpctl	81
timselavg	76
timselmax	76
timselmean	76
timselmin	76
timselpctl	77
timselstd	76
timselsum	76
timselvar	76
timsort	125
timstd	80
timsum	80
timvar	80
trend	104

U

uv2dv	117
uv2dvl	117

V

vct	23
vertavg	75
vertmax	75
vertmean	75
vertmin	75
vertstd	75
vertsum	75
vertvar	75

W

wct	128
-----	-----

Y

ydayavg	93
ydaymax	93
ydaymean	93
ydaymin	93
ydaypctl	94
ydaystd	93
ydaysum	93
ydayvar	93
ydrunavg	99
ydrunmax	99

ydrunmean	99
ydrunmin	99
ydrunpctl	101
ydrunstd	99
ydrunsum	99
ydrunvar	99
yearavg	88
yearmax	88
yearmean	88
yearmin	88
yearpctl	89
yearstd	88
yearsum	88
yearvar	88
yhouravg	92
yhourmax	92
yhourmean	92
yhourmin	92
yhourstd	92
yhoursum	92
yhourvar	92
ymonadd	61
ymonavg	95
ymondiv	61
ymonmax	95
ymonmean	95
ymonmin	95
ymonmul	61
ymonpctl	96
ymonstd	95
ymonsub	61
ymonsum	95
ymonvar	95
yseasavg	97
yseasmax	97
yseasmean	97
yseasmin	97
yseaspctl	98
yseasstd	97
yseassum	97
yseasvar	97

Z

zaxisdes	23
zonavg	71
zonmax	71
zonmean	71
zonmin	71
zonpctl	71
zonstd	71
zonsum	71
zonvar	71