

CDI Fortran Manual

Climate Data Interface
Version 1.5.1
June 2011

Uwe Schulzweida
Max-Planck-Institute for Meteorology

Contents

1. Introduction	5
1.1. Building from sources	5
1.1.1. Compilation	5
1.1.2. Installation	6
2. File Formats	7
2.1. GRIB	7
2.1.1. GRIB edition 1	8
2.1.2. GRIB edition 2	8
2.2. NetCDF	8
2.3. SERVICE	8
2.4. EXTRA	9
2.5. IEG	9
3. Use of the CDI Library	10
3.1. Creating a dataset	10
3.2. Reading a dataset	10
3.3. Compiling and Linking with the CDI library	11
4. CDI modules	13
4.1. Dataset functions	13
4.1.1. Create a new dataset: <code>streamOpenWrite</code>	13
4.1.2. Open a dataset for reading: <code>streamOpenRead</code>	14
4.1.3. Close an open dataset: <code>streamClose</code>	15
4.1.4. Get the filetype: <code>streamInqFiletype</code>	15
4.1.5. Define the byte order: <code>streamDefByteorder</code>	15
4.1.6. Get the byte order: <code>streamInqByteorder</code>	15
4.1.7. Define the variable list: <code>streamDefVlist</code>	16
4.1.8. Get the variable list: <code>streamInqVlist</code>	16
4.1.9. Define time step: <code>streamDefTimestep</code>	16
4.1.10. Get time step: <code>streamInqTimestep</code>	16
4.1.11. Write a variable: <code>streamWriteVar</code>	17
4.1.12. Read a variable: <code>streamReadVar</code>	17
4.1.13. Write a horizontal slice of a variable: <code>streamWriteVarSlice</code>	17
4.1.14. Read a horizontal slice of a variable: <code>streamReadVarSlice</code>	17
4.2. Variable list functions	19
4.2.1. Create a variable list: <code>vlistCreate</code>	19
4.2.2. Destroy a variable list: <code>vlistDestroy</code>	19
4.2.3. Copy a variable list: <code>vlistCopy</code>	19
4.2.4. Duplicate a variable list: <code>vlistDuplicate</code>	19
4.2.5. Concatenate two variable lists: <code>vlistCat</code>	20
4.2.6. Copy some entries of a variable list: <code>vlistCopyFlag</code>	20
4.2.7. Number of variables in a variable list: <code>vlistNvars</code>	20

4.2.8.	Number of grids in a variable list: <code>vlistNgrids</code>	20
4.2.9.	Number of zaxis in a variable list: <code>vlistNzaxis</code>	20
4.2.10.	Define the time axis: <code>vlistDefTaxis</code>	21
4.2.11.	Get the time axis: <code>vlistInqTaxis</code>	21
4.3.	Variable functions	22
4.3.1.	Define a Variable: <code>vlistDefVar</code>	22
4.3.2.	Get the Grid ID of a Variable: <code>vlistInqVarGrid</code>	23
4.3.3.	Get the Zaxis ID of a Variable: <code>vlistInqVarZaxis</code>	23
4.3.4.	Define the code number of a Variable: <code>vlistDefVarCode</code>	23
4.3.5.	Get the Code number of a Variable: <code>vlistInqVarCode</code>	23
4.3.6.	Define the name of a Variable: <code>vlistDefVarName</code>	24
4.3.7.	Get the name of a Variable: <code>vlistInqVarName</code>	24
4.3.8.	Define the long name of a Variable: <code>vlistDefVarLongname</code>	24
4.3.9.	Get the longname of a Variable: <code>vlistInqVarLongname</code>	24
4.3.10.	Define the standard name of a Variable: <code>vlistDefVarStdname</code>	25
4.3.11.	Get the standard name of a Variable: <code>vlistInqVarStdname</code>	25
4.3.12.	Define the units of a Variable: <code>vlistDefVarUnits</code>	25
4.3.13.	Get the units of a Variable: <code>vlistInqVarUnits</code>	26
4.3.14.	Define the data type of a Variable: <code>vlistDefVarDatatype</code>	26
4.3.15.	Get the data type of a Variable: <code>vlistInqVarDatatype</code>	26
4.3.16.	Define the missing value of a Variable: <code>vlistDefVarMissval</code>	27
4.3.17.	Get the missing value of a Variable: <code>vlistInqVarMissval</code>	27
4.4.	Attributes	28
4.4.1.	Get number of variable attributes: <code>vlistInqNatts</code>	28
4.4.2.	Get information about an attribute: <code>vlistInqAtt</code>	28
4.4.3.	Define an integer attribute: <code>vlistDefAttInt</code>	28
4.4.4.	Get the value(s) of an integer attribute: <code>vlistInqAttInt</code>	29
4.4.5.	Define a floating point attribute: <code>vlistDefAttFlt</code>	29
4.4.6.	Get the value(s) of a floating point attribute: <code>vlistInqAttFlt</code>	29
4.4.7.	Define a text attribute: <code>vlistDefAttTxt</code>	30
4.4.8.	Get the value(s) of a text attribute: <code>vlistInqAttTxt</code>	30
4.5.	Grid functions	31
4.5.1.	Create a horizontal Grid: <code>gridCreate</code>	31
4.5.2.	Destroy a horizontal Grid: <code>gridDestroy</code>	32
4.5.3.	Duplicate a horizontal Grid: <code>gridDuplicate</code>	32
4.5.4.	Get the type of a Grid: <code>gridInqType</code>	32
4.5.5.	Get the size of a Grid: <code>gridInqSize</code>	32
4.5.6.	Define the number of values of a X-axis: <code>gridDefXsize</code>	32
4.5.7.	Get the number of values of a X-axis: <code>gridInqXsize</code>	33
4.5.8.	Define the number of values of a Y-axis: <code>gridDefYsize</code>	33
4.5.9.	Get the number of values of a Y-axis: <code>gridInqYsize</code>	33
4.5.10.	Define the values of a X-axis: <code>gridDefXvals</code>	33
4.5.11.	Get all values of a X-axis: <code>gridInqXvals</code>	34
4.5.12.	Define the values of a Y-axis: <code>gridDefYvals</code>	34
4.5.13.	Get all values of a Y-axis: <code>gridInqYvals</code>	34
4.5.14.	Define the bounds of a X-axis: <code>gridDefXbounds</code>	34
4.5.15.	Get the bounds of a X-axis: <code>gridInqXbounds</code>	35
4.5.16.	Define the bounds of a Y-axis: <code>gridDefYbounds</code>	35
4.5.17.	Get the bounds of a Y-axis: <code>gridInqYbounds</code>	35
4.5.18.	Define the name of a X-axis: <code>gridDefXname</code>	35
4.5.19.	Get the name of a X-axis: <code>gridInqXname</code>	36

4.5.20. Define the longname of a X-axis: <code>gridDefXlongname</code>	36
4.5.21. Get the longname of a X-axis: <code>gridInqXlongname</code>	36
4.5.22. Define the units of a X-axis: <code>gridDefXunits</code>	36
4.5.23. Get the units of a X-axis: <code>gridInqXunits</code>	37
4.5.24. Define the name of a Y-axis: <code>gridDefYname</code>	37
4.5.25. Get the name of a Y-axis: <code>gridInqYname</code>	37
4.5.26. Define the longname of a Y-axis: <code>gridDefYlongname</code>	37
4.5.27. Get the longname of a Y-axis: <code>gridInqYlongname</code>	38
4.5.28. Define the units of a Y-axis: <code>gridDefYunits</code>	38
4.5.29. Get the units of a Y-axis: <code>gridInqYunits</code>	38
4.6. Z-axis functions	39
4.6.1. Create a vertical Z-axis: <code>zaxisCreate</code>	39
4.6.2. Destroy a vertical Z-axis: <code>zaxisDestroy</code>	40
4.6.3. Get the type of a Z-axis: <code>zaxisInqType</code>	40
4.6.4. Get the size of a Z-axis: <code>zaxisInqSize</code>	40
4.6.5. Define the levels of a Z-axis: <code>zaxisDefLevels</code>	40
4.6.6. Get all levels of a Z-axis: <code>zaxisInqLevels</code>	40
4.6.7. Get one level of a Z-axis: <code>zaxisInqLevel</code>	41
4.6.8. Define the name of a Z-axis: <code>zaxisDefName</code>	41
4.6.9. Get the name of a Z-axis: <code>zaxisInqName</code>	41
4.6.10. Define the longname of a Z-axis: <code>zaxisDefLongname</code>	42
4.6.11. Get the longname of a Z-axis: <code>zaxisInqLongname</code>	42
4.6.12. Define the units of a Z-axis: <code>zaxisDefUnits</code>	42
4.6.13. Get the units of a Z-axis: <code>zaxisInqUnits</code>	42
4.7. T-axis functions	43
4.7.1. Create a Time axis: <code>taxisCreate</code>	43
4.7.2. Destroy a Time axis: <code>taxisDestroy</code>	44
4.7.3. Define the reference date: <code>taxisDefRdate</code>	44
4.7.4. Get the reference date: <code>taxisInqRdate</code>	44
4.7.5. Define the reference time: <code>taxisDefRtime</code>	44
4.7.6. Get the reference time: <code>taxisInqRtime</code>	44
4.7.7. Define the verification date: <code>taxisDefVdate</code>	45
4.7.8. Get the verification date: <code>taxisInqVdate</code>	45
4.7.9. Define the verification time: <code>taxisDefVtime</code>	45
4.7.10. Get the verification time: <code>taxisInqVtime</code>	45
4.7.11. Define the calendar: <code>taxisDefCalendar</code>	45
4.7.12. Get the calendar: <code>taxisInqCalendar</code>	46
A. Quick Reference	48
B. Examples	62
B.1. Write a dataset	62
B.1.1. Result	64
B.2. Read a dataset	64
B.3. Copy a dataset	65
B.4. Fortran 2003: <code>mo_cdi</code> and <code>iso_c.binding</code>	67

1. Introduction

CDI is an Interface to access Climate and NWP model Data. The interface is independent from a specific data format and has a C and Fortran API. **CDI** was developed for a fast and machine independent access to GRIB and netCDF datasets with the same interface. The local [MPI-MET](#) data formats SERVICE, EXTRA and IEG are also supported.

1.1. Building from sources

This section describes how to build the **CDI** library from the sources on a UNIX system. **CDI** is using the GNU configure and build system to compile the source code. The only requirement is a working ANSI C99 compiler.

First go to the [download](#) page (<http://code.zmaw.de/projects/cdi/files>) to get the latest distribution, if you do not already have it.

To take full advantage of **CDI**'s features the following additional libraries should be installed:

- Unidata [netCDF](#) library (<http://www.unidata.ucar.edu/packages/netcdf>) version 3 or higher. This is needed to read/write netCDF files with **CDI**.
- The ECMWF [GRIB_API](#) (http://www.ecmwf.int/products/data/software/grib_api.html) version 1.9.5 or higher. This library is needed to encode/decode GRIB2 records with **CDI**.

1.1.1. Compilation

Compilation is now done by performing the following steps:

1. Unpack the archive, if you haven't already done that:

```
gunzip cdi-$VERSION.tar.gz      # uncompress the archive
tar xf cdi-$VERSION.tar         # unpack it
cd cdi-$VERSION
```

2. Run the configure script:

```
./configure
```

Or optionally with netCDF support:

```
./configure --with-netcdf=<netCDF root directory>
```

For an overview of other configuration options use

```
./configure --help
```

3. Compile the program by running make:

```
make
```

The software should compile without problems and the **CDI** library (`libcdi.a`) should be available in the `src` directory of the distribution.

1.1.2. Installation

After the compilation of the source code do a `make install`, possibly as root if the destination permissions require that.

```
make install
```

The library is installed into the directory `<prefix>/lib`. The C and Fortran include files are installed into the directory `<prefix>/include`. `<prefix>` defaults to `/usr/local` but can be changed with the `--prefix` option of the configure script.

2. File Formats

2.1. GRIB

GRIB [GRIB] (GRIdded Binary) is a standard format designed by the World Meteorological Organization (WMO) to support the efficient transmission and storage of gridded meteorological data.

A GRIB record consists of a series of header sections, followed by a bitstream of packed data representing one horizontal grid of data values. The header sections are intended to fully describe the data included in the bitstream, specifying information such as the parameter, units, and precision of the data, the grid system and level type on which the data is provided, and the date and time for which the data are valid.

Non-numeric descriptors are enumerated in tables, such that a 1-byte code in a header section refers to a unique description. The WMO provides a standard set of enumerated parameter names and level types, but the standard also allows for the definition of locally used parameters and geometries. Any activity that generates and distributes GRIB records must also make their locally defined GRIB tables available to users.

CDI does not support the full GRIB standard. The following data representation and level types are implemented:

GRIB1 grid type	GRIB2 template	GRIB_API name	description
0	3.0	regular_ll	Regular longitude/latitude grid
3	–	lambert	Lambert conformal grid
4	3.40	regular_gg	Regular Gaussian longitude/latitude grid
4	3.40	reduced_gg	Reduced Gaussian longitude/latitude grid
10	3.1	rotated_ll	Rotated longitude/latitude grid
50	3.50	sh	Spherical harmonic coefficients
192	3.100	–	Icosahedral-hexagonal GME grid
–	3.101	–	General unstructured grid

GRIB1 level type	GRIB2 level type	GRIB_API name	description
1	1	surface	Surface level
99	–	–	Isobaric level in Pa
100	100	isobaricInhPa	Isobaric level in hPa
103	102	heightAboveSea	Altitude above mean sea level
105	103	heightAboveGround	Height level above ground
107	104	sigma	Sigma level
109	105	hybrid	Hybrid level
110	105	hybridLayer	Layer between two hybrid levels
111	106	depthBelowLand	Depth below land surface
112	106	depthBelowLandLayer	Layer between two depths below land surface
113	107	theta	Isentropic (theta) level
160	160	depthBelowSea	Depth below sea level

2.1.1. GRIB edition 1

GRIB1 is implemented in **CDI** as an internal library and enabled per default. The internal GRIB1 library is called CGRIBEX. This is lightweight version of the ECMWF GRIBEX library. CGRIBEX is written in ANSI C with a portable Fortran interface. The configure option `--disable-cgribex` will disable the encoding/decoding of GRIB1 records with CGRIBEX.

2.1.2. GRIB edition 2

GRIB2 is available in **CDI** via the ECMWF GRIB-API [[GRIBAPI](#)]. GRIB-API is an external library and not part of **CDI**. To use GRIB2 with **CDI** the GRIB-API library must be installed before the configuration of the **CDI** library. Use the configure option `--with-grib_api` to enable GRIB2 support.

The GRIB-API library is also used to encode/decode GRIB1 records if the support for the CGRIBEX library is disabled.

2.2. NetCDF

NetCDF [[NetCDF](#)] (Network Common Data Form) is an interface for array-oriented data access and a library that provides an implementation of the interface. The netCDF library also defines a machine-independent format for representing scientific data. Together, the interface, library, and format support the creation, access, and sharing of scientific data.

CDI only supports the classic data model of netCDF and arrays up to 4 dimensions. These dimensions should only be used by the horizontal grid and the time. The netCDF attributes should follow the [GDT](#), [COARDS](#) or [CF Conventions](#).

NetCDF is an external library and not part of **CDI**. To use netCDF with **CDI** the netCDF library must be installed before the configuration of the **CDI** library. Use the configure option `--with-netcdf` to enable netCDF support (see [Build](#)).

2.3. SERVICE

SERVICE is the binary exchange format of the atmospheric general circulation model ECHAM [[ECHAM](#)]. It has a header section with 8 integer values followed by the data section. The header and the data section have the standard Fortran blocking for binary data records. A SERVICE record can have an accuracy of 4 or 8 bytes and the byteorder can be little or big endian. In **CDI** the accuracy of the header and data section must be the same. The following Fortran code example can be used to read a SERVICE record with an accuracy of 4 bytes:

```
INTEGER*4 icode,ilevel,ideate,itime,nlon,nlat,idispo1,idispo2
REAL*4 field(mlon,mlat)
...
READ(unit) icode,ilevel,ideate,itime,nlon,nlat,idispo1,idispo2
READ(unit) ((field(ilon,ilat), ilon=1,nlon), ilat=1,nlat)
```


The constants `m lon` and `m lat` must be greater or equal than `n lon` and `n lat`. The meaning of the variables are:

<code>icode</code>	The code number
<code>ilevel</code>	The level
<code>idate</code>	The date as YYYYMMDD
<code>itime</code>	The time as hhmmss
<code>nlon</code>	The number of longitudes
<code>nlat</code>	The number of latitudes
<code>idispo1</code>	For the users disposal (Not used in CDI)
<code>idispo2</code>	For the users disposal (Not used in CDI)

SERVICE is implemented in **CDI** as an internal library and enabled per default. The configure option `--disable-service` will disable the support for the SERVICE format.

2.4. EXTRA

EXTRA is the standard binary output format of the ocean model MPIOM [[MPIOM](#)]. It has a header section with 4 integer values followed by the data section. The header and the data section have the standard Fortran blocking for binary data records. An EXTRA record can have an accuracy of 4 or 8 bytes and the byteorder can be little or big endian. In **CDI** the accuracy of the header and data section must be the same. The following Fortran code example can be used to read an EXTRA record with an accuracy of 4 bytes:

```
INTEGER*4 idate,icode,ilevel,nsize
REAL*4 field(msize)
...
READ(unit) idate,icode,ilevel,nsize
READ(unit) (field(isize),isize=1,nsize)
```

The constant `msize` must be greater or equal than `nsize`. The meaning of the variables are:

<code>idate</code>	The date as YYYYMMDD
<code>icode</code>	The code number
<code>ilevel</code>	The level
<code>nsize</code>	The size of the field

EXTRA is implemented in **CDI** as an internal library and enabled per default. The configure option `--disable-extra` will disable the support for the EXTRA format.

2.5. IEG

IEG is the standard binary output format of the regional model REMO [[REMO](#)]. It is simple an unpacked GRIB edition 1 format. The product and grid description sections are coded with 4 byte integer values and the data section can have 4 or 8 byte IEEE floating point values. The header and the data section have the standard Fortran blocking for binary data records. The IEG format has a fixed size of 100 for the vertical coordinate table. That means it is not possible to store more than 50 model levels with this format. **CDI** supports only data on Gaussian and LonLat grids for the IEG format.

IEG is implemented in **CDI** as an internal library and enabled per default. The configure option `--disable-ieg` will disable the support for the IEG format.

3. Use of the CDI Library

This chapter provides templates of common sequences of **CDI** calls needed for common uses. For clarity only the names of routines are used. Declarations and error checking were omitted. Statements that are typically invoked multiple times were indented and ... is used to represent arbitrary sequences of other statements. Full parameter lists are described in later chapters. Complete examples for write, read and copy a dataset with **CDI** can be found in [Appendix B](#).

3.1. Creating a dataset

Here is a typical sequence of **CDI** calls used to create a new dataset:

```
gridCreate      ! create a horizontal Grid: from type and size
...
zaxisCreate     ! create a vertical Z-axis: from type and size
...
taxisCreate     ! create a Time axis: from type
...
vlistCreate     ! create a variable list
...
    vlistDefVar  ! define variables: from Grid and Z-axis
...
streamOpenWrite ! create a dataset: from name and file type
...
streamDefVlist  ! define variable list
...
streamDefTimestep ! define time step
...
    streamWriteVar ! write variable
...
streamClose     ! close the dataset
...
vlistDestroy    ! destroy the variable list
...
taxisDestroy    ! destroy the Time axis
...
zaxisDestroy    ! destroy the Z-axis
...
gridDestroy     ! destroy the Grid
```

3.2. Reading a dataset

Here is a typical sequence of **CDI** calls used to read a dataset:

```
streamOpenRead  ! open existing dataset
...
streamInqVlist  ! find out what is in it
...
    vlistInqVarGrid ! get an identifier to the Grid
...
```

```
    vlistInqVarZaxis    ! get an identifier to the Z-axis
    ...
    vlistInqTaxis       ! get an identifier to the T-axis
    ...
    streamInqTimestep   ! get time step
    ...
    streamReadVar       ! read variable
    ...
    streamClose         ! close the dataset
```

3.3. Compiling and Linking with the CDI library

Details of how to compile and link a program that uses the **CDI** C or FORTRAN interfaces differ, depending on the operating system, the available compilers, and where the **CDI** library and include files are installed. Here are examples of how to compile and link a program that uses the **CDI** library on a Unix platform, so that you can adjust these examples to fit your installation. There are two different interfaces for using **CDI** functions in Fortran: `cfortran.h` and the intrinsic `iso_c_binding` module from Fortran 2003 standard. At first, the preparations for compilers without F2003 capabilities are described.

Every FORTRAN file that references **CDI** functions or constants must contain an appropriate `INCLUDE` statement before the first such reference:

```
INCLUDE "cdi.inc"
```

Unless the `cdi.inc` file is installed in a standard directory where FORTRAN compiler always looks, you must use the `-I` option when invoking the compiler, to specify a directory where `cdi.inc` is installed, for example:

```
f77 -c -I/usr/local/cdi/include myprogram.f
```

Alternatively, you could specify an absolute path name in the `INCLUDE` statement, but then your program would not compile on another platform where **CDI** is installed in a different location. Unless the **CDI** library is installed in a standard directory where the linker always looks, you must use the `-L` and `-l` options to link an object file that uses the **CDI** library. For example:

```
f77 -o myprogram myprogram.o -L/usr/local/cdi/lib -lcdi
```

Alternatively, you could specify an absolute path name for the library:

```
f77 -o myprogram myprogram.o -L/usr/local/cdi/lib/libcdi
```

If the **CDI** library is using other external libraries, you must add these libraries in the same way. For example with the `netCDF` library:

```
f77 -o myprogram myprogram.o -L/usr/local/cdi/lib -lcdi \
-L/usr/local/netcdf/lib -lnetcdf
```

For using the `iso_c_bindings` two things are necessary in a program or module

```
USE ISO_C_BINDING
USE mo_cdi
```

The `iso_c_binding` module is included in `mo_cdi`, but without `cfortran.h` characters and character variables have to be handled separately. Examples are available in section [B.4](#).

After installation `mo_cdi.o` and `mo_cdi.mod` are located in the library and header directory respectively. `cdilib.o` has to be mentioned directly on the command line. It can be found in the library directory, too. Depending on the **CDI** configuration, a compile command should look like this:

```
nagf95 -f2003 -g cdi_read_f2003.f90 -L/usr/lib -lnetcdf -o cdi_read_example
-I/usr/local/include
/usr/local/lib/cdilib.o /usr/local/lib/mo_cdi.o
```

4. CDI modules

4.1. Dataset functions

This module contains functions to read and write the data. To create a new dataset the output format must be specified with one of the following predefined file format types:

FILETYPE_GRB	File type GRIB version 1
FILETYPE_GRB2	File type GRIB version 2
FILETYPE_NC	File type netCDF
FILETYPE_NC2	File type netCDF version 2 (64-bit)
FILETYPE_NC4	File type netCDF-4 (HDF5)
FILETYPE_NC4C	File type netCDF-4 classic
FILETYPE_SRV	File type SERVICE
FILETYPE_EXT	File type EXTRA
FILETYPE_IEG	File type IEG

FILETYPE_GRB2 is only available if the **CDI** library was compiled with GRIB_API support and all netCDF file types are only available if the **CDI** library was compiled with netCDF support!

To set the byte order of a binary dataset with the file format type FILETYPE_SRV, FILETYPE_EXT or FILETYPE_IEG use one of the following predefined constants in the call to [streamDefByteorder](#):

CDI_BIGENDIAN	Byte order big endian
CDI_LITTLEENDIAN	Byte order little endian

4.1.1. Create a new dataset: streamOpenWrite

The function `streamOpenWrite` creates a new dataset.

Usage

```
INTEGER FUNCTION streamOpenWrite(CHARACTER*(*) path, INTEGER filetype)
```

<code>path</code>	The name of the new dataset.
<code>filetype</code>	The type of the file format, one of the set of predefined CDI file format types. The valid CDI file format types are FILETYPE_GRB, FILETYPE_GRB2, FILETYPE_NC, FILETYPE_NC2, FILETYPE_NC4, FILETYPE_NC4C, FILETYPE_SRV, FILETYPE_EXT and FILETYPE_IEG.

Result

Upon successful completion `streamOpenWrite` returns an identifier to the open stream. Otherwise, a negative number with the error status is returned.

Errors

CDI_ESYSTEM	Operating system error.
CDI_EINVAL	Invalid argument.
CDI_EUFILETYPE	Unsupported file type.
CDI_ELIBNAVAIL	Library support not compiled in.

Example

Here is an example using `streamOpenWrite` to create a new netCDF file named `foo.nc` for writing:

```
INCLUDE 'cdi.h'
...
INTEGER streamID
...
streamID = streamOpenWrite("foo.nc", FILETYPE_NC)
IF ( streamID .LT. 0 ) CALL handle_error(streamID)
...
```

4.1.2. Open a dataset for reading: streamOpenRead

The function `streamOpenRead` opens an existing dataset for reading.

Usage

```
INTEGER FUNCTION streamOpenRead(CHARACTER*(*) path)
```

`path` The name of the dataset to be read.

Result

Upon successful completion `streamOpenRead` returns an identifier to the open stream. Otherwise, a negative number with the error status is returned.

Errors

CDI_ESYSTEM	Operating system error.
CDI_EINVAL	Invalid argument.
CDI_EUFILETYPE	Unsupported file type.
CDI_ELIBNAVAIL	Library support not compiled in.

Example

Here is an example using `streamOpenRead` to open an existing netCDF file named `foo.nc` for reading:

```
INCLUDE 'cdi.h'
...
INTEGER streamID
...
streamID = streamOpenRead("foo.nc")
IF ( streamID .LT. 0 ) CALL handle_error(streamID)
...
```

4.1.3. Close an open dataset: `streamClose`

The function `streamClose` closes an open dataset.

Usage

```
SUBROUTINE streamClose(INTEGER streamID)
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

4.1.4. Get the filetype: `streamInqFiletype`

The function `streamInqFiletype` returns the filetype of a stream.

Usage

```
INTEGER FUNCTION streamInqFiletype(INTEGER streamID)
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

Result

`streamInqFiletype` returns the type of the file format, one of the set of predefined **CDI** file format types. The valid **CDI** file format types are `FILETYPE_GRB`, `FILETYPE_GRB2`, `FILETYPE_NC`, `FILETYPE_NC2`, `FILETYPE_NC4`, `FILETYPE_NC4C`, `FILETYPE_SRV`, `FILETYPE_EXT` and `FILETYPE_IEG`.

4.1.5. Define the byte order: `streamDefByteorder`

The function `streamDefByteorder` defines the byte order of a binary dataset with the file format type `FILETYPE_SRV`, `FILETYPE_EXT` or `FILETYPE_IEG`.

Usage

```
SUBROUTINE streamDefByteorder(INTEGER streamID, INTEGER byteorder)
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

`byteorder` The byte order of a dataset, one of the **CDI** constants `CDI_BIGENDIAN` and `CDI_LITTLEENDIAN`.

4.1.6. Get the byte order: `streamInqByteorder`

The function `streamInqByteorder` returns the byte order of a binary dataset with the file format type `FILETYPE_SRV`, `FILETYPE_EXT` or `FILETYPE_IEG`.

Usage

```
INTEGER FUNCTION streamInqByteorder(INTEGER streamID)
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

Result

`streamInqByteorder` returns the type of the byte order. The valid **CDI** byte order types are `CDI_BIGENDIAN` and `CDI_LITTLEENDIAN`

4.1.7. Define the variable list: `streamDefVlist`

The function `streamDefVlist` defines the variable list of a stream.

Usage

```
SUBROUTINE streamDefVlist(INTEGER streamID, INTEGER vlistID)
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

`vlistID` Variable list ID, from a previous call to [vlistCreate](#).

4.1.8. Get the variable list: `streamInqVlist`

The function `streamInqVlist` returns the variable list of a stream.

Usage

```
INTEGER FUNCTION streamInqVlist(INTEGER streamID)
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

Result

`streamInqVlist` returns an identifier to the variable list.

4.1.9. Define time step: `streamDefTimestep`

The function `streamDefTimestep` defines the time step of a stream.

Usage

```
INTEGER FUNCTION streamDefTimestep(INTEGER streamID, INTEGER tsID)
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

`tsID` Timestep identifier.

Result

`streamDefTimestep` returns the number of records of the time step.

4.1.10. Get time step: `streamInqTimestep`

The function `streamInqTimestep` returns the time step of a stream.

Usage

```
INTEGER FUNCTION streamInqTimestep(INTEGER streamID, INTEGER tsID)
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

`tsID` Timestep identifier.

Result

`streamInqTimestep` returns the number of records of the time step.

4.1.11. Write a variable: streamWriteVar

The function streamWriteVar writes the values of one time step of a variable to an open dataset.

Usage

```
SUBROUTINE streamWriteVar(INTEGER streamID, INTEGER varID, const REAL*8 data,  
                          INTEGER nmiss)
```

streamID Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).
varID Variable identifier.
data Pointer to a block of data values to be written.
nmiss Number of missing values.

4.1.12. Read a variable: streamReadVar

The function streamReadVar reads all the values of one time step of a variable from an open dataset.

Usage

```
SUBROUTINE streamReadVar(INTEGER streamID, INTEGER varID, REAL*8 data,  
                        INTEGER nmiss)
```

streamID Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).
varID Variable identifier.
data Pointer to the location into which the data values are read. The caller must allocate space for the returned values.
nmiss Number of missing values.

4.1.13. Write a horizontal slice of a variable: streamWriteVarSlice

The function streamWriteVarSlice writes the values of a horizontal slice of a variable to an open dataset.

Usage

```
SUBROUTINE streamWriteVarSlice(INTEGER streamID, INTEGER varID, INTEGER levelID,  
                              const REAL*8 data, INTEGER nmiss)
```

streamID Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).
varID Variable identifier.
levelID Level identifier.
data Pointer to a block of data values to be written.
nmiss Number of missing values.

4.1.14. Read a horizontal slice of a variable: streamReadVarSlice

The function streamReadVar reads all the values of a horizontal slice of a variable from an open dataset.

Usage

```
SUBROUTINE streamReadVarSlice(INTEGER streamID, INTEGER varID, INTEGER levelID,  
                             REAL*8 data, INTEGER nmiss)
```

streamID Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).
varID Variable identifier.
levelID Level identifier.
data Pointer to the location into which the data values are read. The caller must allocate space for the returned values.
nmiss Number of missing values.

4.2. Variable list functions

This module contains functions to handle a list of variables. A variable list is a collection of all variables of a dataset.

4.2.1. Create a variable list: `vlistCreate`

Usage

```
INTEGER FUNCTION vlistCreate()
```

Example

Here is an example using `vlistCreate` to create a variable list and add a variable with `vlistDefVar`.

```
INCLUDE 'cdi.h'
...
INTEGER vlistID, varID
...
vlistID = vlistCreate()
varID = vlistDefVar(vlistID, gridID, zaxisID, TIME_VARIABLE)
...
streamDefVlist(streamID, vlistID)
...
vlistDestroy(vlistID)
...
```

4.2.2. Destroy a variable list: `vlistDestroy`

Usage

```
SUBROUTINE vlistDestroy(INTEGER vlistID)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`

4.2.3. Copy a variable list: `vlistCopy`

The function `vlistCopy` copies all entries from `vlistID1` to `vlistID2`.

Usage

```
SUBROUTINE vlistCopy(INTEGER vlistID2, INTEGER vlistID1)
```

`vlistID2` Target variable list ID

`vlistID1` Source variable list ID

4.2.4. Duplicate a variable list: `vlistDuplicate`

The function `vlistDuplicate` duplicates the variable list from `vlistID1`.

Usage

```
INTEGER FUNCTION vlistDuplicate(INTEGER vlistID)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`

Result

`vlistDuplicate` returns an identifier to the duplicated variable list.

4.2.5. Concatenate two variable lists: `vlistCat`

Concatenate the variable list `vlistID1` at the end of `vlistID2`.

Usage

```
SUBROUTINE vlistCat(INTEGER vlistID2, INTEGER vlistID1)
vlistID2  Target variable list ID
vlistID1  Source variable list ID
```

4.2.6. Copy some entries of a variable list: `vlistCopyFlag`

The function `vlistCopyFlag` copies all entries with a flag from `vlistID1` to `vlistID2`.

Usage

```
SUBROUTINE vlistCopyFlag(INTEGER vlistID2, INTEGER vlistID1)
vlistID2  Target variable list ID
vlistID1  Source variable list ID
```

4.2.7. Number of variables in a variable list: `vlistNvars`

The function `vlistNvars` returns the number of variables in the variable list `vlistID`.

Usage

```
INTEGER FUNCTION vlistNvars(INTEGER vlistID)
vlistID  Variable list ID, from a previous call to vlistCreate
```

Result

`vlistNvars` returns the number of variables in a variable list.

4.2.8. Number of grids in a variable list: `vlistNgrids`

The function `vlistNgrids` returns the number of grids in the variable list `vlistID`.

Usage

```
INTEGER FUNCTION vlistNgrids(INTEGER vlistID)
vlistID  Variable list ID, from a previous call to vlistCreate
```

Result

`vlistNgrids` returns the number of grids in a variable list.

4.2.9. Number of zaxis in a variable list: `vlistNzaxis`

The function `vlistNzaxis` returns the number of zaxis in the variable list `vlistID`.

Usage

```
INTEGER FUNCTION vlistNzaxis(INTEGER vlistID)
```

`vlistID` Variable list ID, from a previous call to [vlistCreate](#)

Result

`vlistNzaxis` returns the number of zaxis in a variable list.

4.2.10. Define the time axis: vlistDefTaxis

The function `vlistDefTaxis` defines the time axis of a variable list.

Usage

```
SUBROUTINE vlistDefTaxis(INTEGER vlistID, INTEGER taxisID)
```

`vlistID` Variable list ID, from a previous call to [vlistCreate](#)

`taxisID` Time axis ID, from a previous call to [taxisCreate](#)

4.2.11. Get the time axis: vlistInqTaxis

The function `vlistInqTaxis` returns the time axis of a variable list.

Usage

```
INTEGER FUNCTION vlistInqTaxis(INTEGER vlistID)
```

`vlistID` Variable list ID, from a previous call to [vlistCreate](#)

Result

`vlistInqTaxis` returns an identifier to the time axis.

4.3. Variable functions

This module contains functions to add new variables to a variable list and to get information about variables from a variable list. To add new variables to a variables list one of the following time types must be specified:

<code>TIME_CONSTANT</code>	For time constant variables
<code>TIME_VARIABLE</code>	For time varying variables

The default data type is 16 bit for GRIB and 32 bit for all other file format types. To change the data type use one of the following predefined constants:

<code>DATATYPE_PACK8</code>	8 packed bit (only for GRIB)
<code>DATATYPE_PACK16</code>	16 packed bit (only for GRIB)
<code>DATATYPE_PACK24</code>	24 packed bit (only for GRIB)
<code>DATATYPE_FLT32</code>	32 bit floating point
<code>DATATYPE_FLT64</code>	64 bit floating point
<code>DATATYPE_INT8</code>	8 bit integer
<code>DATATYPE_INT16</code>	16 bit integer
<code>DATATYPE_INT32</code>	32 bit integer

4.3.1. Define a Variable: `vlistDefVar`

The function `vlistDefVar` adds a new variable to `vlistID`.

Usage

```
INTEGER FUNCTION vlistDefVar(INTEGER vlistID, INTEGER gridID, INTEGER zaxisID,
                             INTEGER timeID)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.
`gridID` Grid ID, from a previous call to `gridCreate`.
`zaxisID` Z-axis ID, from a previous call to `zaxisCreate`.
`timeID` One of the set of predefined **CDI** time identifiers. The valid **CDI** time identifiers are `TIME_CONSTANT` and `TIME_VARIABLE`.

Result

`vlistDefVar` returns an identifier to the new variable.

Example

Here is an example using `vlistCreate` to create a variable list and add a variable with `vlistDefVar`.

```
INCLUDE 'cdi.h'
...
INTEGER vlistID, varID
...
vlistID = vlistCreate()
varID = vlistDefVar(vlistID, gridID, zaxisID, TIME_VARIABLE)
...
streamDefVlist(streamID, vlistID)
...
vlistDestroy(vlistID)
```

...

4.3.2. Get the Grid ID of a Variable: `vlistInqVarGrid`

The function `vlistInqVarGrid` returns the grid ID of a variable.

Usage

```
INTEGER FUNCTION vlistInqVarGrid(INTEGER vlistID, INTEGER varID)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

Result

`vlistInqVarGrid` returns the grid ID of the variable.

4.3.3. Get the Zaxis ID of a Variable: `vlistInqVarZaxis`

The function `vlistInqVarZaxis` returns the zaxis ID of a variable.

Usage

```
INTEGER FUNCTION vlistInqVarZaxis(INTEGER vlistID, INTEGER varID)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

Result

`vlistInqVarZaxis` returns the zaxis ID of the variable.

4.3.4. Define the code number of a Variable: `vlistDefVarCode`

The function `vlistDefVarCode` defines the code number of a variable.

Usage

```
SUBROUTINE vlistDefVarCode(INTEGER vlistID, INTEGER varID, INTEGER code)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`code` Code number.

4.3.5. Get the Code number of a Variable: `vlistInqVarCode`

The function `vlistInqVarCode` returns the code number of a variable.

Usage

```
INTEGER FUNCTION vlistInqVarCode(INTEGER vlistID, INTEGER varID)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

Result

`vlistInqVarCode` returns the code number of the variable.

4.3.6. Define the name of a Variable: `vlistDefVarName`

The function `vlistDefVarName` defines the name of a variable.

Usage

```
SUBROUTINE vlistDefVarName(INTEGER vlistID, INTEGER varID, CHARACTER*(*) name)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`name` Name of the variable.

4.3.7. Get the name of a Variable: `vlistInqVarName`

The function `vlistInqVarName` returns the name of a variable.

Usage

```
SUBROUTINE vlistInqVarName(INTEGER vlistID, INTEGER varID, CHARACTER*(*) name)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`name` Returned variable name. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the pre-defined constant `CDLMAX_NAME`.

Result

`vlistInqVarName` returns the name of the variable to the parameter `name` if available, otherwise the result is an empty string.

4.3.8. Define the long name of a Variable: `vlistDefVarLongname`

The function `vlistDefVarLongname` defines the long name of a variable.

Usage

```
SUBROUTINE vlistDefVarLongname(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) longname)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`longname` Long name of the variable.

4.3.9. Get the longname of a Variable: `vlistInqVarLongname`

The function `vlistInqVarLongname` returns the longname of a variable if available, otherwise the result is an empty string.

Usage

```
SUBROUTINE vlistInqVarLongname(INTEGER vlistID, INTEGER varID,  
                               CHARACTER*(*) longname)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier.
longname Long name of the variable. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`vlistInqVaeLongname` returns the longname of the variable to the parameter `longname`.

4.3.10. Define the standard name of a Variable: `vlistDefVarStdname`

The function `vlistDefVarStdname` defines the standard name of a variable.

Usage

```
SUBROUTINE vlistDefVarStdname(INTEGER vlistID, INTEGER varID,  
                              CHARACTER*(*) stdname)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier.
stdname Standard name of the variable.

4.3.11. Get the standard name of a Variable: `vlistInqVarStdname`

The function `vlistInqVarStdname` returns the standard name of a variable if available, otherwise the result is an empty string.

Usage

```
SUBROUTINE vlistInqVarStdname(INTEGER vlistID, INTEGER varID,  
                              CHARACTER*(*) stdname)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier.
stdname Standard name of the variable. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`vlistInqVarName` returns the standard name of the variable to the parameter `stdname`.

4.3.12. Define the units of a Variable: `vlistDefVarUnits`

The function `vlistDefVarUnits` defines the units of a variable.

Usage

```
SUBROUTINE vlistDefVarUnits(INTEGER vlistID, INTEGER varID, CHARACTER*(*) units)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).

varID Variable identifier.

units Units of the variable.

4.3.13. Get the units of a Variable: vlistInqVarUnits

The function `vlistInqVarUnits` returns the units of a variable if available, otherwise the result is an empty string.

Usage

```
SUBROUTINE vlistInqVarUnits(INTEGER vlistID, INTEGER varID, CHARACTER*(*) units)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).

varID Variable identifier.

units Units of the variable. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`vlistInqVarUnits` returns the units of the variable to the parameter `units`.

4.3.14. Define the data type of a Variable: vlistDefVarDatatype

The function `vlistDefVarDatatype` defines the data type of a variable.

Usage

```
SUBROUTINE vlistDefVarDatatype(INTEGER vlistID, INTEGER varID, INTEGER datatype)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).

varID Variable identifier.

datatype The data type identifier. The valid **CDI** data types are `DATATYPE_PACK8`, `DATATYPE_PACK16`, `DATATYPE_PACK24`, `DATATYPE_FLT32`, `DATATYPE_FLT64`, `DATATYPE_INT8`, `DATATYPE_INT16` and `DATATYPE_INT32`.

4.3.15. Get the data type of a Variable: vlistInqVarDatatype

The function `vlistInqVarDatatype` returns the data type of a variable.

Usage

```
INTEGER FUNCTION vlistInqVarDatatype(INTEGER vlistID, INTEGER varID)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).

varID Variable identifier.

Result

`vlistInqVarDatatype` returns an identifier to the data type of the variable. The valid **CDI** data types are `DATATYPE_PACK8`, `DATATYPE_PACK16`, `DATATYPE_PACK24`, `DATATYPE_FLT32`, `DATATYPE_FLT64`, `DATATYPE_INT8`, `DATATYPE_INT16` and `DATATYPE_INT32`.

4.3.16. Define the missing value of a Variable: `vlistDefVarMissval`

The function `vlistDefVarMissval` defines the missing value of a variable.

Usage

```
SUBROUTINE vlistDefVarMissval(INTEGER vlistID, INTEGER varID, REAL*8 missval)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`missval` Missing value.

4.3.17. Get the missing value of a Variable: `vlistInqVarMissval`

The function `vlistInqVarMissval` returns the missing value of a variable.

Usage

```
REAL*8 FUNCTION vlistInqVarMissval(INTEGER vlistID, INTEGER varID)
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

Result

`vlistInqVarMissval` returns the missing value of the variable.

4.4. Attributes

Attributes may be associated with each variable to specify non CDI standard properties. CDI standard properties as code, name, units, and missing value are directly associated with each variable by the corresponding CDI function (e.g. [vlistDefVarName](#)). An attribute has a variable to which it is assigned, a name, a type, a length, and a sequence of one or more values. The attributes have to be defined after the variable is created and before the variable list is associated with a stream. Attributes are only used for netCDF datasets.

It is also possible to have attributes that are not associated with any variable. These are called global attributes and are identified by using `CDI_GLOBAL` as a variable pseudo-ID. Global attributes are usually related to the dataset as a whole.

CDI supports integer, floating point and text attributes. The data types are defined by the following predefined constants:

```
DATATYPE_INT16  16-bit integer attribute
DATATYPE_INT32  32-bit integer attribute
DATATYPE_FLT32  32-bit floating point attribute
DATATYPE_FLT64  64-bit floating point attribute
DATATYPE_TXT    Text attribute
```

4.4.1. Get number of variable attributes: `vlistInqNatts`

The function `vlistInqNatts` gets the number of variable attributes assigned to this variable.

Usage

```
INTEGER FUNCTION vlistInqNatts(INTEGER vlistID, INTEGER varID, INTEGER nattsp)

vlistID  Variable list ID, from a previous call to vlistCreate.
varID    Variable identifier, or CDI_GLOBAL for a global attribute.
nattsp   Pointer to location for returned number of variable attributes.
```

4.4.2. Get information about an attribute: `vlistInqAtt`

The function `vlistInqNatts` gets information about an attribute.

Usage

```
INTEGER FUNCTION vlistInqAtt(INTEGER vlistID, INTEGER varID, INTEGER attnum,
                             CHARACTER*(*) name, INTEGER typep, INTEGER lenp)

vlistID  Variable list ID, from a previous call to vlistCreate.
varID    Variable identifier, or CDI_GLOBAL for a global attribute.
attnum   Attribute number (from 0 to natts-1).
name     Pointer to the location for the returned attribute name. The caller must allocate
         space for the returned string. The maximum possible length, in characters, of
         the string is given by the predefined constant CDI_MAX_NAME.
typep    Pointer to location for returned attribute type.
lenp     Pointer to location for returned attribute number.
```

4.4.3. Define an integer attribute: `vlistDefAttInt`

The function `vlistDefAttInt` defines an integer attribute.

Usage

```
INTEGER FUNCTION vlistDefAttInt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER type, INTEGER len,  
                                const INTEGER ip)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or CDI_GLOBAL for a global attribute.
name Attribute name.
type External data type (DATATYPE_INT16 or DATATYPE_INT32).
len Number of values provided for the attribute.
ip Pointer to one or more integer values.

4.4.4. Get the value(s) of an integer attribute: vlistInqAttInt

The function `vlistInqAttInt` gets the values(s) of an integer attribute.

Usage

```
INTEGER FUNCTION vlistInqAttInt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER mlen, INTEGER ip)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or CDI_GLOBAL for a global attribute.
name Attribute name.
mlen Number of allocated values provided for the attribute.
ip Pointer location for returned integer attribute value(s).

4.4.5. Define a floating point attribute: vlistDefAttFlt

The function `vlistDefAttFlt` defines a floating point attribute.

Usage

```
INTEGER FUNCTION vlistDefAttFlt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER type, INTEGER len,  
                                const REAL*8 dp)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or CDI_GLOBAL for a global attribute.
name Attribute name.
type External data type (DATATYPE_FLT32 or DATATYPE_FLT64).
len Number of values provided for the attribute.
dp Pointer to one or more floating point values.

4.4.6. Get the value(s) of a floating point attribute: vlistInqAttFlt

The function `vlistInqAttFlt` gets the values(s) of a floating point attribute.

Usage

```
INTEGER FUNCTION vlistInqAttFlt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER mlen, INTEGER dp)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or CDI_GLOBAL for a global attribute.
name Attribute name.
mlen Number of allocated values provided for the attribute.
dp Pointer location for returned floating point attribute value(s).

4.4.7. Define a text attribute: vlistDefAttTxt

The function `vlistDefAttTxt` defines a text attribute.

Usage

```
INTEGER FUNCTION vlistDefAttTxt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER len,  
                                CHARACTER*(*) tp)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or CDI_GLOBAL for a global attribute.
name Attribute name.
len Number of values provided for the attribute.
tp Pointer to one or more character values.

4.4.8. Get the value(s) of a text attribute: vlistInqAttTxt

The function `vlistInqAttTxt` gets the values(s) of a text attribute.

Usage

```
INTEGER FUNCTION vlistInqAttTxt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER mlen, INTEGER tp)
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or CDI_GLOBAL for a global attribute.
name Attribute name.
mlen Number of allocated values provided for the attribute.
tp Pointer location for returned text attribute value(s).

4.5. Grid functions

This module contains functions to define a new horizontal Grid and to get information from an existing Grid. A Grid object is necessary to define a variable. The following different Grid types are available:

GRID_GENERIC	Generic user defined grid
GRID_LONLAT	Regular longitude/latitude grid
GRID_GAUSSIAN	Regular Gaussian lon/lat grid
GRID_SPECTRAL	Spherical harmonic coefficients
GRID_GME	Icosahedral-hexagonal GME grid
GRID_CURVILINEAR	Curvilinear grid
GRID_UNSTRUCTURED	Unstructured grid
GRID_LCC	Lambert conformal conic grid
GRID_REFERENCE	Grid reference number

4.5.1. Create a horizontal Grid: `gridCreate`

The function `gridCreate` creates a horizontal Grid.

Usage

```
INTEGER FUNCTION gridCreate(INTEGER gridtype, INTEGER size)
```

gridtype The type of the grid, one of the set of predefined **CDI** grid types. The valid **CDI** grid types are `GRID_GENERIC`, `GRID_GAUSSIAN`, `GRID_LONLAT`, `GRID_LCC`, `GRID_SPECTRAL`, `GRID_GME`, `GRID_CURVILINEAR`, `GRID_UNSTRUCTURED` and `GRID_REFERENCE`

size Number of gridpoints.

Result

`gridCreate` returns an identifier to the Grid.

Example

Here is an example using `gridCreate` to create a regular lon/lat Grid:

```
INCLUDE 'cdi.h'
...
#define nlon 12
#define nlat 6
...
REAL*8 lons(nlon) = (/0, 30, 60, 90, 120, 150, 180, 210, 240, 270, 300, 330/)
REAL*8 lats(nlat) = (/ -75, -45, -15, 15, 45, 75/)
INTEGER gridID
...
gridID = gridCreate(GRID_LONLAT, nlon*nlat)
CALL gridDefXsize(gridID, nlon)
CALL gridDefYsize(gridID, nlat)
CALL gridDefXvals(gridID, lons)
CALL gridDefYvals(gridID, lats)
...
```

4.5.2. Destroy a horizontal Grid: `gridDestroy`

Usage

```
SUBROUTINE gridDestroy(INTEGER gridID)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

4.5.3. Duplicate a horizontal Grid: `gridDuplicate`

The function `gridDuplicate` duplicates a horizontal Grid.

Usage

```
INTEGER FUNCTION gridDuplicate(INTEGER gridID)
```

`gridID` Grid ID, from a previous call to [gridCreate](#), [gridDuplicate](#) or [vlistInqVarGrid](#).

Result

`gridDuplicate` returns an identifier to the duplicated Grid.

4.5.4. Get the type of a Grid: `gridInqType`

The function `gridInqType` returns the type of a Grid.

Usage

```
INTEGER FUNCTION gridInqType(INTEGER gridID)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

Result

`gridInqType` returns the type of the grid, one of the set of predefined **CDI** grid types. The valid **CDI** grid types are `GRID_GENERIC`, `GRID_GAUSSIAN`, `GRID_LONLAT`, `GRID_LCC`, `GRID_SPECTRAL`, `GRID_GME`, `GRID_CURVILINEAR`, `GRID_UNSTRUCTURED` and `GRID_REFERENCE`.

4.5.5. Get the size of a Grid: `gridInqSize`

The function `gridInqSize` returns the size of a Grid.

Usage

```
INTEGER FUNCTION gridInqSize(INTEGER gridID)
```

`gridID` Grid ID, from a previous call to [gridCreate](#)

Result

`gridInqSize` returns the number of grid points of a Grid.

4.5.6. Define the number of values of a X-axis: `gridDefXsize`

The function `gridDefXsize` defines the number of values of a X-axis.

Usage

```
SUBROUTINE gridDefXsize(INTEGER gridID, INTEGER xsize)
```

gridID Grid ID, from a previous call to [gridCreate](#).

xsize Number of values of a X-axis.

4.5.7. Get the number of values of a X-axis: gridInqXsize

The function `gridInqXsize` returns the number of values of a X-axis.

Usage

```
SUBROUTINE gridInqXsize(INTEGER gridID)
```

gridID Grid ID, from a previous call to [gridCreate](#).

Result

`gridInqXsize` returns the number of values of a X-axis.

4.5.8. Define the number of values of a Y-axis: gridDefYsize

The function `gridDefYsize` defines the number of values of a Y-axis.

Usage

```
SUBROUTINE gridDefYsize(INTEGER gridID, INTEGER ysize)
```

gridID Grid ID, from a previous call to [gridCreate](#).

ysize Number of values of a Y-axis.

4.5.9. Get the number of values of a Y-axis: gridInqYsize

The function `gridInqYsize` returns the number of values of a Y-axis.

Usage

```
SUBROUTINE gridInqYsize(INTEGER gridID)
```

gridID Grid ID, from a previous call to [gridCreate](#).

Result

`gridInqYsize` returns the number of values of a Y-axis.

4.5.10. Define the values of a X-axis: gridDefXvals

The function `gridDefXvals` defines all values of the X-axis.

Usage

```
SUBROUTINE gridDefXvals(INTEGER gridID, const REAL*8 xvals)
```

gridID Grid ID, from a previous call to [gridCreate](#).

xvals X-values of the grid.

4.5.11. Get all values of a X-axis: `gridInqXvals`

The function `gridInqXvals` returns all values of the X-axis.

Usage

```
INTEGER FUNCTION gridInqXvals(INTEGER gridID, REAL*8 xvals)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`xvals` Pointer to the location into which the X-values are read. The caller must allocate space for the returned values.

Result

Upon successful completion `gridInqXvals` returns the number of values and the values are stored in `xvals`. Otherwise, 0 is returned and `xvals` is empty.

4.5.12. Define the values of a Y-axis: `gridDefYvals`

The function `gridDefYvals` defines all values of the Y-axis.

Usage

```
SUBROUTINE gridDefYvals(INTEGER gridID, const REAL*8 yvals)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`yvals` Y-values of the grid.

4.5.13. Get all values of a Y-axis: `gridInqYvals`

The function `gridInqYvals` returns all values of the Y-axis.

Usage

```
INTEGER FUNCTION gridInqYvals(INTEGER gridID, REAL*8 yvals)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`yvals` Pointer to the location into which the Y-values are read. The caller must allocate space for the returned values.

Result

Upon successful completion `gridInqYvals` returns the number of values and the values are stored in `yvals`. Otherwise, 0 is returned and `yvals` is empty.

4.5.14. Define the bounds of a X-axis: `gridDefXbounds`

The function `gridDefXbounds` defines all bounds of the X-axis.

Usage

```
SUBROUTINE gridDefXbounds(INTEGER gridID, const REAL*8 xbounds)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`xbounds` X-bounds of the grid.

4.5.15. Get the bounds of a X-axis: gridInqXbounds

The function `gridInqXbounds` returns the bounds of the X-axis.

Usage

```
INTEGER FUNCTION gridInqXbounds(INTEGER gridID, REAL*8 xbounds)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`xbounds` Pointer to the location into which the X-bounds are read. The caller must allocate space for the returned values.

Result

Upon successful completion `gridInqXbounds` returns the number of bounds and the bounds are stored in `xbounds`. Otherwise, 0 is returned and `xbounds` is empty.

4.5.16. Define the bounds of a Y-axis: gridDefYbounds

The function `gridDefYbounds` defines all bounds of the Y-axis.

Usage

```
SUBROUTINE gridDefYbounds(INTEGER gridID, const REAL*8 ybounds)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`ybounds` Y-bounds of the grid.

4.5.17. Get the bounds of a Y-axis: gridInqYbounds

The function `gridInqYbounds` returns the bounds of the Y-axis.

Usage

```
INTEGER FUNCTION gridInqYbounds(INTEGER gridID, REAL*8 ybounds)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`ybounds` Pointer to the location into which the Y-bounds are read. The caller must allocate space for the returned values.

Result

Upon successful completion `gridInqYbounds` returns the number of bounds and the bounds are stored in `ybounds`. Otherwise, 0 is returned and `ybounds` is empty.

4.5.18. Define the name of a X-axis: gridDefXname

The function `gridDefXname` defines the name of a X-axis.

Usage

```
SUBROUTINE gridDefXname(INTEGER gridID, CHARACTER*(*) name)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`name` Name of the X-axis.

4.5.19. Get the name of a X-axis: gridInqXname

The function `gridInqXname` returns the name of a X-axis.

Usage

```
SUBROUTINE gridInqXname(INTEGER gridID, CHARACTER*(*) name)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`name` Name of the X-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqXname` returns the name of the X-axis to the parameter `name`.

4.5.20. Define the longname of a X-axis: gridDefXlongname

The function `gridDefXlongname` defines the longname of a X-axis.

Usage

```
SUBROUTINE gridDefXlongname(INTEGER gridID, CHARACTER*(*) longname)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`longname` Longname of the X-axis.

4.5.21. Get the longname of a X-axis: gridInqXlongname

The function `gridInqXlongname` returns the longname of a X-axis.

Usage

```
SUBROUTINE gridInqXlongname(INTEGER gridID, CHARACTER*(*) longname)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`longname` Longname of the X-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqXlongname` returns the longname of the X-axis to the parameter `longname`.

4.5.22. Define the units of a X-axis: gridDefXunits

The function `gridDefXunits` defines the units of a X-axis.

Usage

```
SUBROUTINE gridDefXunits(INTEGER gridID, CHARACTER*(*) units)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`units` Units of the X-axis.

4.5.23. Get the units of a X-axis: `gridInqXunits`

The function `gridInqXunits` returns the units of a X-axis.

Usage

```
SUBROUTINE gridInqXunits(INTEGER gridID, CHARACTER*(*) units)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`units` Units of the X-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqXunits` returns the units of the X-axis to the parameter `units`.

4.5.24. Define the name of a Y-axis: `gridDefYname`

The function `gridDefYname` defines the name of a Y-axis.

Usage

```
SUBROUTINE gridDefYname(INTEGER gridID, CHARACTER*(*) name)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`name` Name of the Y-axis.

4.5.25. Get the name of a Y-axis: `gridInqYname`

The function `gridInqYname` returns the name of a Y-axis.

Usage

```
SUBROUTINE gridInqYname(INTEGER gridID, CHARACTER*(*) name)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`name` Name of the Y-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqYname` returns the name of the Y-axis to the parameter `name`.

4.5.26. Define the longname of a Y-axis: `gridDefYlongname`

The function `gridDefYlongname` defines the longname of a Y-axis.

Usage

```
SUBROUTINE gridDefYlongname(INTEGER gridID, CHARACTER*(*) longname)
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`longname` Longname of the Y-axis.

4.5.27. Get the longname of a Y-axis: gridInqYlongname

The function `gridInqYlongname` returns the longname of a Y-axis.

Usage

```
SUBROUTINE gridInqXlongname(INTEGER gridID, CHARACTER*(*) longname)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`longname` Longname of the Y-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqYlongname` returns the longname of the Y-axis to the parameter `longname`.

4.5.28. Define the units of a Y-axis: gridDefYunits

The function `gridDefYunits` defines the units of a Y-axis.

Usage

```
SUBROUTINE gridDefYunits(INTEGER gridID, CHARACTER*(*) units)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`units` Units of the Y-axis.

4.5.29. Get the units of a Y-axis: gridInqYunits

The function `gridInqYunits` returns the units of a Y-axis.

Usage

```
SUBROUTINE gridInqYunits(INTEGER gridID, CHARACTER*(*) units)
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`units` Units of the Y-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqYunits` returns the units of the Y-axis to the parameter `units`.

4.6. Z-axis functions

This section contains functions to define a new vertical Z-axis and to get information from an existing Z-axis. A Z-axis object is necessary to define a variable. The following different Z-axis types are available:

ZAXIS_GENERIC	Generic user defined level
ZAXIS_SURFACE	Surface level
ZAXIS_HYBRID	Hybrid level
ZAXIS_SIGMA	Sigma level
ZAXIS_PRESSURE	Isobaric pressure level in Pascal
ZAXIS_HEIGHT	Height above ground in meters
ZAXIS_ALTITUDE	Altitude above mean sea level in meters
ZAXIS_DEPTH_BELOW_SEA	Depth below sea level in meters
ZAXIS_DEPTH_BELOW_LAND	Depth below land surface in centimeters

4.6.1. Create a vertical Z-axis: `zaxisCreate`

The function `zaxisCreate` creates a vertical Z-axis.

Usage

```
INTEGER FUNCTION zaxisCreate(INTEGER zaxistype, INTEGER size)
```

zaxistype The type of the Z-axis, one of the set of predefined **CDI** Z-axis types. The valid **CDI** Z-axis types are `ZAXIS_GENERIC`, `ZAXIS_SURFACE`, `ZAXIS_HYBRID`, `ZAXIS_SIGMA`, `ZAXIS_PRESSURE`, `ZAXIS_HEIGHT`, `ZAXIS_DEPTH_BELOW_SEA` and `ZAXIS_DEPTH_BELOW_LAND`.

size Number of levels.

Result

`zaxisCreate` returns an identifier to the Z-axis.

Example

Here is an example using `zaxisCreate` to create a pressure level Z-axis:

```
INCLUDE 'cdi.h'
...
#define nlev 5
...
REAL*8 levs(nlev) = (/101300, 92500, 85000, 50000, 20000/)
INTEGER zaxisID
...
zaxisID = zaxisCreate(ZAXIS_PRESSURE, nlev)
CALL zaxisDefLevels(zaxisID, levs)
...
```

4.6.2. Destroy a vertical Z-axis: `zaxisDestroy`

Usage

```
SUBROUTINE zaxisDestroy(INTEGER zaxisID)
```

`zaxisID` Z-axis ID, from a previous call to [zaxisCreate](#).

4.6.3. Get the type of a Z-axis: `zaxisInqType`

The function `zaxisInqType` returns the type of a Z-axis.

Usage

```
INTEGER FUNCTION zaxisInqType(INTEGER zaxisID)
```

`zaxisID` Z-axis ID, from a previous call to [zaxisCreate](#).

Result

`zaxisInqType` returns the type of the Z-axis, one of the set of predefined **CDI** Z-axis types. The valid **CDI** Z-axis types are `ZAXIS_GENERIC`, `ZAXIS_SURFACE`, `ZAXIS_HYBRID`, `ZAXIS_SIGMA`, `ZAXIS_PRESSURE`, `ZAXIS_HEIGHT`, `ZAXIS_DEPTH_BELOW_SEA` and `ZAXIS_DEPTH_BELOW_LAND`.

4.6.4. Get the size of a Z-axis: `zaxisInqSize`

The function `zaxisInqSize` returns the size of a Z-axis.

Usage

```
INTEGER FUNCTION zaxisInqSize(INTEGER zaxisID)
```

`zaxisID` Z-axis ID, from a previous call to [zaxisCreate](#)

Result

`zaxisInqSize` returns the number of levels of a Z-axis.

4.6.5. Define the levels of a Z-axis: `zaxisDefLevels`

The function `zaxisDefLevels` defines the levels of a Z-axis.

Usage

```
SUBROUTINE zaxisDefLevels(INTEGER zaxisID, const REAL*8 levels)
```

`zaxisID` Z-axis ID, from a previous call to [zaxisCreate](#).

`levels` All levels of the Z-axis.

4.6.6. Get all levels of a Z-axis: `zaxisInqLevels`

The function `zaxisInqLevels` returns all levels of a Z-axis.

Usage

```
SUBROUTINE zaxisInqLevels(INTEGER zaxisID, REAL*8 levels)
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

levels Pointer to the location into which the levels are read. The caller must allocate space for the returned values.

Result

`zaxisInqLevels` saves all levels to the parameter `levels`.

4.6.7. Get one level of a Z-axis: `zaxisInqLevel`

The function `zaxisInqLevel` returns one level of a Z-axis.

Usage

```
REAL*8 FUNCTION zaxisInqLevel(INTEGER zaxisID, INTEGER levelID)
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

levelID Level index (range: 0 to `nlevel-1`).

Result

`zaxisInqLevel` returns the level of a Z-axis.

4.6.8. Define the name of a Z-axis: `zaxisDefName`

The function `zaxisDefName` defines the name of a Z-axis.

Usage

```
SUBROUTINE zaxisDefName(INTEGER zaxisID, CHARACTER*(*) name)
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

name Name of the Z-axis.

4.6.9. Get the name of a Z-axis: `zaxisInqName`

The function `zaxisInqName` returns the name of a Z-axis.

Usage

```
SUBROUTINE zaxisInqName(INTEGER zaxisID, CHARACTER*(*) name)
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

name Name of the Z-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`zaxisInqName` returns the name of the Z-axis to the parameter `name`.

4.6.10. Define the longname of a Z-axis: `zaxisDefLongname`

The function `zaxisDefLongname` defines the longname of a Z-axis.

Usage

```
SUBROUTINE zaxisDefLongname(INTEGER zaxisID, CHARACTER*(*) longname)
```

`zaxisID` Z-axis ID, from a previous call to `zaxisCreate`.

`longname` Longname of the Z-axis.

4.6.11. Get the longname of a Z-axis: `zaxisInqLongname`

The function `zaxisInqLongname` returns the longname of a Z-axis.

Usage

```
SUBROUTINE zaxisInqLongname(INTEGER zaxisID, CHARACTER*(*) longname)
```

`zaxisID` Z-axis ID, from a previous call to `zaxisCreate`.

`longname` Longname of the Z-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`zaxisInqLongname` returns the longname of the Z-axis to the parameter `longname`.

4.6.12. Define the units of a Z-axis: `zaxisDefUnits`

The function `zaxisDefUnits` defines the units of a Z-axis.

Usage

```
SUBROUTINE zaxisDefUnits(INTEGER zaxisID, CHARACTER*(*) units)
```

`zaxisID` Z-axis ID, from a previous call to `zaxisCreate`.

`units` Units of the Z-axis.

4.6.13. Get the units of a Z-axis: `zaxisInqUnits`

The function `zaxisInqUnits` returns the units of a Z-axis.

Usage

```
SUBROUTINE zaxisInqUnits(INTEGER zaxisID, CHARACTER*(*) units)
```

`zaxisID` Z-axis ID, from a previous call to `zaxisCreate`

`units` Units of the Z-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`zaxisInqUnits` returns the units of the Z-axis to the parameter `units`.

4.7. T-axis functions

This section contains functions to define a new Time axis and to get information from an existing T-axis. A T-axis object is necessary to define the time axis of a dataset and must be assigned to a variable list using `vlistDefTaxis`. The following different Time axis types are available:

<code>TAXIS_ABSOLUTE</code>	Absolute time axis
<code>TAXIS_RELATIVE</code>	Relative time axis

An absolute time axis has the current time to each time step. It can be used without knowledge of the calendar.

A relative time is the time relative to a fixed reference time. The current time results from the reference time and the elapsed interval. The result depends on the used calendar. CDI supports the following calendar types:

<code>CALENDAR_STANDARD</code>	Mixed Gregorian/Julian calendar.
<code>CALENDAR_PROLEPTIC</code>	Proleptic Gregorian calendar. This is the default.
<code>CALENDAR_360DAYS</code>	All years are 360 days divided into 30 day months.
<code>CALENDAR_365DAYS</code>	Gregorian calendar without leap years, i.e., all years are 365 days long.
<code>CALENDAR_366DAYS</code>	Gregorian calendar with every year being a leap year, i.e., all years are 366 days long.

4.7.1. Create a Time axis: `taxisCreate`

The function `taxisCreate` creates a Time axis.

Usage

```
INTEGER FUNCTION taxisCreate(INTEGER taxistype)
```

taxistype The type of the Time axis, one of the set of predefined **CDI** time axis types. The valid **CDI** time axis types are `TAXIS_ABSOLUTE` and `TAXIS_RELATIVE`.

Result

`taxisCreate` returns an identifier to the Time axis.

Example

Here is an example using `taxisCreate` to create a relative T-axis with a standard calendar.

```
INCLUDE 'cdi.h'
...
INTEGER taxisID
...
taxisID = taxisCreate(TAXIS_RELATIVE)
taxisDefCalendar(taxisID, CALENDAR_STANDARD)
taxisDefRdate(taxisID, 19850101)
taxisDefRtime(taxisID, 120000)
...
```

4.7.2. Destroy a Time axis: `taxisDestroy`

Usage

```
SUBROUTINE taxisDestroy(INTEGER taxisID)
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

4.7.3. Define the reference date: `taxisDefRdate`

The function `taxisDefVdate` defines the reference date of a Time axis.

Usage

```
SUBROUTINE taxisDefRdate(INTEGER taxisID, INTEGER rdate)
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

`rdate` Reference date (YYYYMMDD)

4.7.4. Get the reference date: `taxisInqRdate`

The function `taxisInqRdate` returns the reference date of a Time axis.

Usage

```
INTEGER FUNCTION taxisInqRdate(INTEGER taxisID)
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

Result

`taxisInqVdate` returns the reference date.

4.7.5. Define the reference time: `taxisDefRtime`

The function `taxisDefVdate` defines the reference time of a Time axis.

Usage

```
SUBROUTINE taxisDefRtime(INTEGER taxisID, INTEGER rtime)
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

`rtime` Reference time (hhmmss)

4.7.6. Get the reference time: `taxisInqRtime`

The function `taxisInqRtime` returns the reference time of a Time axis.

Usage

```
INTEGER FUNCTION taxisInqRtime(INTEGER taxisID)
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

Result

`taxisInqVtime` returns the reference time.

4.7.7. Define the verification date: `taxisDefVdate`

The function `taxisDefVdate` defines the verification date of a Time axis.

Usage

```
SUBROUTINE taxisDefVdate(INTEGER taxisID, INTEGER vdate)

taxisID  Time axis ID, from a previous call to taxisCreate
vdate    Verification date (YYYYMMDD)
```

4.7.8. Get the verification date: `taxisInqVdate`

The function `taxisInqVdate` returns the verification date of a Time axis.

Usage

```
INTEGER FUNCTION taxisInqVdate(INTEGER taxisID)

taxisID  Time axis ID, from a previous call to taxisCreate
```

Result

`taxisInqVdate` returns the verification date.

4.7.9. Define the verification time: `taxisDefVtime`

The function `taxisDefVtime` defines the verification time of a Time axis.

Usage

```
SUBROUTINE taxisDefVtime(INTEGER taxisID, INTEGER vtime)

taxisID  Time axis ID, from a previous call to taxisCreate
vtime    Verification time (hhmmss)
```

4.7.10. Get the verification time: `taxisInqVtime`

The function `taxisInqVtime` returns the verification time of a Time axis.

Usage

```
INTEGER FUNCTION taxisInqVtime(INTEGER taxisID)

taxisID  Time axis ID, from a previous call to taxisCreate
```

Result

`taxisInqVtime` returns the verification time.

4.7.11. Define the calendar: `taxisDefCalendar`

The function `taxisDefCalendar` defines the calendar of a Time axis.

Usage

```
SUBROUTINE taxisDefCalendar(INTEGER taxisID, INTEGER calendar)
```

taxisID Time axis ID, from a previous call to [taxisCreate](#)

calendar The type of the calendar, one of the set of predefined **CDI** calendar types. The valid **CDI** calendar types are `CALENDAR_STANDARD`, `CALENDAR_PROLEPTIC`, `CALENDAR_360DAYS`, `CALENDAR_365DAYS` and `CALENDAR_366DAYS`.

4.7.12. Get the calendar: taxisInqCalendar

The function `taxisInqCalendar` returns the calendar of a Time axis.

Usage

```
INTEGER FUNCTION taxisInqCalendar(INTEGER taxisID)
```

taxisID Time axis ID, from a previous call to [taxisCreate](#)

Result

`taxisInqCalendar` returns the type of the calendar, one of the set of predefined **CDI** calendar types. The valid **CDI** calendar types are `CALENDAR_STANDARD`, `CALENDAR_PROLEPTIC`, `CALENDAR_360DAYS`, `CALENDAR_365DAYS` and `CALENDAR_366DAYS`.

Bibliography

[ECHAM]

The atmospheric general circulation model ECHAM5, from the [Max Planck Institute for Meteorologie](#)

[GRIB]

[GRIB version 1](#), from the World Meteorological Organisation ([WMO](#))

[GRIBAPI]

[GRIB API decoding/encoding](#), from the European Centre for Medium-Range Weather Forecasts ([ECMWF](#))

[HDF5]

[HDF version 5](#), from the HDF Group

[NetCDF]

[NetCDF Software Package](#), from the [UNIDATA](#) Program Center of the University Corporation for Atmospheric Research

[MPIOM]

The ocean model MPIOM, from the [Max Planck Institute for Meteorologie](#)

[REMO]

The regional climate model REMO, from the [Max Planck Institute for Meteorologie](#)

A. Quick Reference

This appendix provide a brief listing of the Fortran language bindings of the CDI library routines:

`gridCreate`

```
INTEGER FUNCTION gridCreate(INTEGER gridtype, INTEGER size)
```

Create a horizontal Grid

`gridDefXbounds`

```
SUBROUTINE gridDefXbounds(INTEGER gridID, const REAL*8 xbounds)
```

Define the bounds of a X-axis

`gridDefXlongname`

```
SUBROUTINE gridDefXlongname(INTEGER gridID, CHARACTER*(*) longname)
```

Define the longname of a X-axis

`gridDefXname`

```
SUBROUTINE gridDefXname(INTEGER gridID, CHARACTER*(*) name)
```

Define the name of a X-axis

`gridDefXsize`

```
SUBROUTINE gridDefXsize(INTEGER gridID, INTEGER xsize)
```

Define the number of values of a X-axis

`gridDefXunits`

```
SUBROUTINE gridDefXunits(INTEGER gridID, CHARACTER*(*) units)
```

Define the units of a X-axis

`gridDefXvals`

```
SUBROUTINE gridDefXvals(INTEGER gridID, const REAL*8 xvals)
```

Define the values of a X-axis

gridDefYbounds

```
SUBROUTINE gridDefYbounds(INTEGER gridID, const REAL*8 ybounds)
```

Define the bounds of a Y-axis

gridDefYlongname

```
SUBROUTINE gridDefYlongname(INTEGER gridID, CHARACTER*(*) longname)
```

Define the longname of a Y-axis

gridDefYname

```
SUBROUTINE gridDefYname(INTEGER gridID, CHARACTER*(*) name)
```

Define the name of a Y-axis

gridDefYsize

```
SUBROUTINE gridDefYsize(INTEGER gridID, INTEGER ysize)
```

Define the number of values of a Y-axis

gridDefYunits

```
SUBROUTINE gridDefYunits(INTEGER gridID, CHARACTER*(*) units)
```

Define the units of a Y-axis

gridDefYvals

```
SUBROUTINE gridDefYvals(INTEGER gridID, const REAL*8 yvals)
```

Define the values of a Y-axis

gridDestroy

```
SUBROUTINE gridDestroy(INTEGER gridID)
```

Destroy a horizontal Grid

gridDuplicate

```
INTEGER FUNCTION gridDuplicate(INTEGER gridID)
```

Duplicate a horizontal Grid

gridInqSize

```
INTEGER FUNCTION gridInqSize(INTEGER gridID)
```

Get the size of a Grid

gridInqType

```
INTEGER FUNCTION gridInqType(INTEGER gridID)
```

Get the type of a Grid

gridInqXbounds

```
INTEGER FUNCTION gridInqXbounds(INTEGER gridID, REAL*8 xbounds)
```

Get the bounds of a X-axis

gridInqXlongname

```
SUBROUTINE gridInqXlongname(INTEGER gridID, CHARACTER*(*) longname)
```

Get the longname of a X-axis

gridInqXname

```
SUBROUTINE gridInqXname(INTEGER gridID, CHARACTER*(*) name)
```

Get the name of a X-axis

gridInqXsize

```
SUBROUTINE gridInqXsize(INTEGER gridID)
```

Get the number of values of a X-axis

gridInqXunits

```
SUBROUTINE gridInqXunits(INTEGER gridID, CHARACTER*(*) units)
```

Get the units of a X-axis

gridInqXvals

```
INTEGER FUNCTION gridInqXvals(INTEGER gridID, REAL*8 xvals)
```

Get all values of a X-axis

gridInqYbounds

```
INTEGER FUNCTION gridInqYbounds(INTEGER gridID, REAL*8 ybounds)
```

Get the bounds of a Y-axis

gridInqYlongname

```
SUBROUTINE gridInqXlongname(INTEGER gridID, CHARACTER*(*) longname)
```

Get the longname of a Y-axis

gridInqYname

```
SUBROUTINE gridInqYname(INTEGER gridID, CHARACTER*(*) name)
```

Get the name of a Y-axis

gridInqYsize

```
SUBROUTINE gridInqYsize(INTEGER gridID)
```

Get the number of values of a Y-axis

gridInqYunits

```
SUBROUTINE gridInqYunits(INTEGER gridID, CHARACTER*(*) units)
```

Get the units of a Y-axis

gridInqYvals

```
INTEGER FUNCTION gridInqYvals(INTEGER gridID, REAL*8 yvals)
```

Get all values of a Y-axis

streamClose

```
SUBROUTINE streamClose(INTEGER streamID)
```

Close an open dataset

streamDefByteorder

```
SUBROUTINE streamDefByteorder(INTEGER streamID, INTEGER byteorder)
```

Define the byte order

`streamDefTimestep`

```
INTEGER FUNCTION streamDefTimestep(INTEGER streamID, INTEGER tsID)
```

Define time step

`streamDefVlist`

```
SUBROUTINE streamDefVlist(INTEGER streamID, INTEGER vlistID)
```

Define the variable list

`streamInqByteorder`

```
INTEGER FUNCTION streamInqByteorder(INTEGER streamID)
```

Get the byte order

`streamInqFiletype`

```
INTEGER FUNCTION streamInqFiletype(INTEGER streamID)
```

Get the filetype

`streamInqTimestep`

```
INTEGER FUNCTION streamInqTimestep(INTEGER streamID, INTEGER tsID)
```

Get time step

`streamInqVlist`

```
INTEGER FUNCTION streamInqVlist(INTEGER streamID)
```

Get the variable list

`streamOpenRead`

```
INTEGER FUNCTION streamOpenRead(CHARACTER*(*) path)
```

Open a dataset for reading

`streamOpenWrite`

```
INTEGER FUNCTION streamOpenWrite(CHARACTER*(*) path, INTEGER filetype)
```

Create a new dataset

streamReadVar

```
SUBROUTINE streamReadVar(INTEGER streamID, INTEGER varID, REAL*8 data,  
                        INTEGER nmiss)
```

Read a variable

streamReadVarSlice

```
SUBROUTINE streamReadVarSlice(INTEGER streamID, INTEGER varID, INTEGER levelID,  
                             REAL*8 data, INTEGER nmiss)
```

Read a horizontal slice of a variable

streamWriteVar

```
SUBROUTINE streamWriteVar(INTEGER streamID, INTEGER varID, const REAL*8 data,  
                         INTEGER nmiss)
```

Write a variable

streamWriteVarSlice

```
SUBROUTINE streamWriteVarSlice(INTEGER streamID, INTEGER varID, INTEGER levelID,  
                              const REAL*8 data, INTEGER nmiss)
```

Write a horizontal slice of a variable

taxisCreate

```
INTEGER FUNCTION taxisCreate(INTEGER taxistype)
```

Create a Time axis

taxisDefCalendar

```
SUBROUTINE taxisDefCalendar(INTEGER taxisID, INTEGER calendar)
```

Define the calendar

taxisDefRdate

```
SUBROUTINE taxisDefRdate(INTEGER taxisID, INTEGER rdate)
```

Define the reference date

taxisDefRtime

```
SUBROUTINE taxisDefRtime(INTEGER taxisID, INTEGER rtime)
```

Define the reference time

`taxisDefVdate`

```
SUBROUTINE taxisDefVdate(INTEGER taxisID, INTEGER vdate)
```

Define the verification date

`taxisDefVtime`

```
SUBROUTINE taxisDefVtime(INTEGER taxisID, INTEGER vtime)
```

Define the verification time

`taxisDestroy`

```
SUBROUTINE taxisDestroy(INTEGER taxisID)
```

Destroy a Time axis

`taxisInqCalendar`

```
INTEGER FUNCTION taxisInqCalendar(INTEGER taxisID)
```

Get the calendar

`taxisInqRdate`

```
INTEGER FUNCTION taxisInqRdate(INTEGER taxisID)
```

Get the reference date

`taxisInqRtime`

```
INTEGER FUNCTION taxisInqRtime(INTEGER taxisID)
```

Get the reference time

`taxisInqVdate`

```
INTEGER FUNCTION taxisInqVdate(INTEGER taxisID)
```

Get the verification date

`taxisInqVtime`

```
INTEGER FUNCTION taxisInqVtime(INTEGER taxisID)
```

Get the verification time

vlistCat

```
SUBROUTINE vlistCat(INTEGER vlistID2, INTEGER vlistID1)
```

Concatenate two variable lists

vlistCopy

```
SUBROUTINE vlistCopy(INTEGER vlistID2, INTEGER vlistID1)
```

Copy a variable list

vlistCopyFlag

```
SUBROUTINE vlistCopyFlag(INTEGER vlistID2, INTEGER vlistID1)
```

Copy some entries of a variable list

vlistCreate

```
INTEGER FUNCTION vlistCreate()
```

Create a variable list

vlistDefAttFlt

```
INTEGER FUNCTION vlistDefAttFlt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER type, INTEGER len,  
                                const REAL*8 dp)
```

Define a floating point attribute

vlistDefAttInt

```
INTEGER FUNCTION vlistDefAttInt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER type, INTEGER len,  
                                const INTEGER ip)
```

Define an integer attribute

vlistDefAttTxt

```
INTEGER FUNCTION vlistDefAttTxt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER len,  
                                CHARACTER*(*) tp)
```

Define a text attribute

`vlistDefTaxis`

```
SUBROUTINE vlistDefTaxis(INTEGER vlistID, INTEGER taxisID)
```

Define the time axis

`vlistDefVar`

```
INTEGER FUNCTION vlistDefVar(INTEGER vlistID, INTEGER gridID, INTEGER zaxisID,  
                             INTEGER timeID)
```

Define a Variable

`vlistDefVarCode`

```
SUBROUTINE vlistDefVarCode(INTEGER vlistID, INTEGER varID, INTEGER code)
```

Define the code number of a Variable

`vlistDefVarDatatype`

```
SUBROUTINE vlistDefVarDatatype(INTEGER vlistID, INTEGER varID, INTEGER datatype)
```

Define the data type of a Variable

`vlistDefVarLongname`

```
SUBROUTINE vlistDefVarLongname(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) longname)
```

Define the long name of a Variable

`vlistDefVarMissval`

```
SUBROUTINE vlistDefVarMissval(INTEGER vlistID, INTEGER varID, REAL*8 missval)
```

Define the missing value of a Variable

`vlistDefVarName`

```
SUBROUTINE vlistDefVarName(INTEGER vlistID, INTEGER varID, CHARACTER*(*) name)
```

Define the name of a Variable

`vlistDefVarStdname`

```
SUBROUTINE vlistDefVarStdname(INTEGER vlistID, INTEGER varID,  
                               CHARACTER*(*) stdname)
```

Define the standard name of a Variable

`vlistDefVarUnits`

```
SUBROUTINE vlistDefVarUnits(INTEGER vlistID, INTEGER varID, CHARACTER*(*) units)
```

Define the units of a Variable

`vlistDestroy`

```
SUBROUTINE vlistDestroy(INTEGER vlistID)
```

Destroy a variable list

`vlistDuplicate`

```
INTEGER FUNCTION vlistDuplicate(INTEGER vlistID)
```

Duplicate a variable list

`vlistInqAtt`

```
INTEGER FUNCTION vlistInqAtt(INTEGER vlistID, INTEGER varID, INTEGER attnum,  
                             CHARACTER*(*) name, INTEGER typep, INTEGER lenp)
```

Get information about an attribute

`vlistInqAttFlt`

```
INTEGER FUNCTION vlistInqAttFlt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER mlen, INTEGER dp)
```

Get the value(s) of a floating point attribute

`vlistInqAttInt`

```
INTEGER FUNCTION vlistInqAttInt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER mlen, INTEGER ip)
```

Get the value(s) of an integer attribute

`vlistInqAttTxt`

```
INTEGER FUNCTION vlistInqAttTxt(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) name, INTEGER mlen, INTEGER tp)
```

Get the value(s) of a text attribute

`vlistInqNatts`

```
INTEGER FUNCTION vlistInqNatts(INTEGER vlistID, INTEGER varID, INTEGER nattsp)
```

Get number of variable attributes

`vlistInqTaxis`

```
INTEGER FUNCTION vlistInqTaxis(INTEGER vlistID)
```

Get the time axis

`vlistInqVarCode`

```
INTEGER FUNCTION vlistInqVarCode(INTEGER vlistID, INTEGER varID)
```

Get the Code number of a Variable

`vlistInqVarDatatype`

```
INTEGER FUNCTION vlistInqVarDatatype(INTEGER vlistID, INTEGER varID)
```

Get the data type of a Variable

`vlistInqVarGrid`

```
INTEGER FUNCTION vlistInqVarGrid(INTEGER vlistID, INTEGER varID)
```

Get the Grid ID of a Variable

`vlistInqVarLongname`

```
SUBROUTINE vlistInqVarLongname(INTEGER vlistID, INTEGER varID,  
                                CHARACTER*(*) longname)
```

Get the longname of a Variable

`vlistInqVarMissval`

```
REAL*8 FUNCTION vlistInqVarMissval(INTEGER vlistID, INTEGER varID)
```

Get the missing value of a Variable

`vlistInqVarName`

```
SUBROUTINE vlistInqVarName(INTEGER vlistID, INTEGER varID, CHARACTER*(*) name)
```

Get the name of a Variable

`vlistInqVarStdname`

```
SUBROUTINE vlistInqVarStdname(INTEGER vlistID, INTEGER varID,  
                               CHARACTER*(*) stdname)
```

Get the standard name of a Variable

[vlistInqVarUnits](#)

```
SUBROUTINE vlistInqVarUnits(INTEGER vlistID, INTEGER varID, CHARACTER*(*) units)
```

Get the units of a Variable

[vlistInqVarZaxis](#)

```
INTEGER FUNCTION vlistInqVarZaxis(INTEGER vlistID, INTEGER varID)
```

Get the Zaxis ID of a Variable

[vlistNgrids](#)

```
INTEGER FUNCTION vlistNgrids(INTEGER vlistID)
```

Number of grids in a variable list

[vlistNvars](#)

```
INTEGER FUNCTION vlistNvars(INTEGER vlistID)
```

Number of variables in a variable list

[vlistNzaxis](#)

```
INTEGER FUNCTION vlistNzaxis(INTEGER vlistID)
```

Number of zaxis in a variable list

[zaxisCreate](#)

```
INTEGER FUNCTION zaxisCreate(INTEGER zaxistype, INTEGER size)
```

Create a vertical Z-axis

[zaxisDefLevels](#)

```
SUBROUTINE zaxisDefLevels(INTEGER zaxisID, const REAL*8 levels)
```

Define the levels of a Z-axis

[zaxisDefLongname](#)

```
SUBROUTINE zaxisDefLongname(INTEGER zaxisID, CHARACTER*(*) longname)
```

Define the longname of a Z-axis

zaxisDefName

```
SUBROUTINE zaxisDefName(INTEGER zaxisID, CHARACTER*(*) name)
```

Define the name of a Z-axis

zaxisDefUnits

```
SUBROUTINE zaxisDefUnits(INTEGER zaxisID, CHARACTER*(*) units)
```

Define the units of a Z-axis

zaxisDestroy

```
SUBROUTINE zaxisDestroy(INTEGER zaxisID)
```

Destroy a vertical Z-axis

zaxisInqLevel

```
REAL*8 FUNCTION zaxisInqLevel(INTEGER zaxisID, INTEGER levelID)
```

Get one level of a Z-axis

zaxisInqLevels

```
SUBROUTINE zaxisInqLevels(INTEGER zaxisID, REAL*8 levels)
```

Get all levels of a Z-axis

zaxisInqLongname

```
SUBROUTINE zaxisInqLongname(INTEGER zaxisID, CHARACTER*(*) longname)
```

Get the longname of a Z-axis

zaxisInqName

```
SUBROUTINE zaxisInqName(INTEGER zaxisID, CHARACTER*(*) name)
```

Get the name of a Z-axis

zaxisInqSize

```
INTEGER FUNCTION zaxisInqSize(INTEGER zaxisID)
```

Get the size of a Z-axis

[zaxisInqType](#)

```
INTEGER FUNCTION zaxisInqType(INTEGER zaxisID)
```

Get the type of a Z-axis

[zaxisInqUnits](#)

```
SUBROUTINE zaxisInqUnits(INTEGER zaxisID, CHARACTER*(*) units)
```

Get the units of a Z-axis

B. Examples

This appendix contains complete examples to write, read and copy a dataset with the **CDI** library.

B.1. Write a dataset

Here is an example using **CDI** to write a netCDF dataset with 2 variables on 3 time steps. The first variable is a 2D field on surface level and the second variable is a 3D field on 5 pressure levels. Both variables are on the same lon/lat grid.

```
PROGRAM CDIWRITE

IMPLICIT NONE

5  INCLUDE 'cdi.inc'

INTEGER nlon, nlat, nlev, nts
PARAMETER (nlon = 12) ! Number of longitudes
PARAMETER (nlat = 6) ! Number of latitudes
10 PARAMETER (nlev = 5) ! Number of levels
PARAMETER (nts = 3) ! Number of time steps

INTEGER gridID, zaxisID1, zaxisID2, taxisID
INTEGER vlistID, varID1, varID2, streamID, tsID
15 INTEGER i, nmiss, status
REAL*8 lons(nlon), lats(nlat), levs(nlev)
REAL*8 var1(nlon*nlat), var2(nlon*nlat*nlev)

DATA lons /0, 30, 60, 90, 120, 150, 180, 210, 240, 270, 300, 330/
20 DATA lats /-75, -45, -15, 15, 45, 75/
DATA levs /101300, 92500, 85000, 50000, 20000/

nmiss = 0

25 ! Create a regular lon/lat grid
gridID = gridCreate(GRID_LONLAT, nlon*nlat)
CALL gridDefXsize(gridID, nlon)
CALL gridDefYsize(gridID, nlat)
CALL gridDefXvals(gridID, lons)
30 CALL gridDefYvals(gridID, lats)

! Create a surface level Z-axis
zaxisID1 = zaxisCreate(ZAXIS_SURFACE, 1)

35 ! Create a pressure level Z-axis
zaxisID2 = zaxisCreate(ZAXIS_PRESSURE, nlev)
CALL zaxisDefLevels(zaxisID2, levs)

! Create a variable list
40 vlistID = vlistCreate()
```

```

!   Define the variables
varID1 = vlistDefVar(vlistID, gridID, zaxisID1, TIME_VARIABLE)
varID2 = vlistDefVar(vlistID, gridID, zaxisID2, TIME_VARIABLE)
45
!   Define the variable names
CALL vlistDefVarName(vlistID, varID1, "varname1")
CALL vlistDefVarName(vlistID, varID2, "varname2")

50 !   Create a Time axis
    taxisID = taxisCreate(TAXIS_ABSOLUTE)

!   Assign the Time axis to the variable list
CALL vlistDefTaxis(vlistID, taxisID)
55
!   Create a dataset in netCDF fromat
streamID = streamOpenWrite("example.nc", FILETYPE_NC)
IF ( streamID < 0 ) THEN
    WRITE(0,*) cdiStringError(streamID)
60    STOP
    END IF

!   Assign the variable list to the dataset
CALL streamDefVlist(streamID, vlistID)
65
!   Loop over the number of time steps
DO tsID = 0, nts-1
!       Set the verification date to 1985-01-01 + tsID
CALL taxisDefVdate(taxisID, 19850101+tsID)
70 !       Set the verification time to 12:00:00
CALL taxisDefVtime(taxisID, 120000)
!       Define the time step
status = streamDefTimestep(streamID, tsID)

75 !       Init var1 and var2
DO i = 1, nlon*nlat
    var1(i) = 1.1
END DO
DO i = 1, nlon*nlat*nlev
80    var2(i) = 2.2
END DO

!       Write var1 and var2
CALL streamWriteVar(streamID, varID1, var1, nmiss)
85 CALL streamWriteVar(streamID, varID2, var2, nmiss)
END DO

!   Close the output stream
CALL streamClose(streamID)
90
!   Destroy the objects
CALL vlistDestroy(vlistID)
CALL taxisDestroy(taxisID)
CALL zaxisDestroy(zaxisID1)
95 CALL zaxisDestroy(zaxisID2)
CALL gridDestroy(gridID)

END

```

B.1.1. Result

This is the `ncdump -h` output of the resulting netCDF file `example.nc`.

```

netcdf example {
2  dimensions:
    lon = 12 ;
    lat = 6 ;
    lev = 5 ;
    time = UNLIMITED ; // (3 currently)
7  variables:
    double lon(lon) ;
        lon:long_name = "longitude" ;
        lon:units = "degrees_east" ;
        lon:standard_name = "longitude" ;
12   double lat(lat) ;
        lat:long_name = "latitude" ;
        lat:units = "degrees_north" ;
        lat:standard_name = "latitude" ;
    double lev(lev) ;
17   lev:long_name = "pressure" ;
        lev:units = "Pa" ;
    double time(time) ;
        time:units = "day as %Y%m%d.%f" ;
    float varname1(time, lat, lon) ;
22   float varname2(time, lev, lat, lon) ;
data:

    lon = 0, 30, 60, 90, 120, 150, 180, 210, 240, 270, 300, 330 ;
27   lat = -75, -45, -15, 15, 45, 75 ;

    lev = 101300, 92500, 85000, 50000, 20000 ;

    time = 19850101.5, 19850102.5, 19850103.5 ;
32 }

```

B.2. Read a dataset

This example reads the netCDF file `example.nc` from [Appendix B.1](#).

```

PROGRAM CDIREAD

3  IMPLICIT NONE

    INCLUDE 'cdi.inc'

    INTEGER nlon, nlat, nlev, nts
8  PARAMETER (nlon = 12) ! Number of longitudes
    PARAMETER (nlat = 6) ! Number of latitudes
    PARAMETER (nlev = 5) ! Number of levels
    PARAMETER (nts = 3) ! Number of time steps

13  INTEGER gridID, zaxisID1, zaxisID2, taxisID
    INTEGER vlistID, varID1, varID2, streamID, tsID
    INTEGER nmiss, status, vdate, vtime
    REAL*8 var1(nlon*nlat), var2(nlon*nlat*nlev)

```



```

18  !   Open the dataset
    streamID = streamOpenRead("example.nc")
    IF ( streamID < 0 ) THEN
        WRITE(0,*) cdiStringError(streamID)
        STOP
23  END IF

    !   Get the variable list of the dataset
    vlistID = streamInqVlist(streamID)

28  !   Set the variable IDs
    varID1 = 0
    varID2 = 1

    !   Get the Time axis from the variable list
33  taxisID = vlistInqTaxis(vlistID)

    !   Loop over the number of time steps
    DO tsID = 0, nts-1
        !   Inquire the time step
38  status = streamInqTimestep(streamID, tsID)

        !   Get the verification date and time
        vdate = taxisInqVdate(taxisID)
        vtime = taxisInqVtime(taxisID)
43

        !   Read var1 and var2
        CALL streamReadVar(streamID, varID1, var1, nmiss)
        CALL streamReadVar(streamID, varID2, var2, nmiss)
48  END DO

    !   Close the input stream
    CALL streamClose(streamID)

    END

```

B.3. Copy a dataset

This example reads the netCDF file `example.nc` from [Appendix B.1](#) and writes the result to a GRIB dataset by simple setting the output file type to `FILETYPE_GRB`.

```

PROGRAM CDICOPY

3  IMPLICIT NONE

    INCLUDE 'cdi.inc'

    INTEGER nlon, nlat, nlev, nts
8  PARAMETER (nlon = 12) ! Number of longitudes
    PARAMETER (nlat = 6) ! Number of latitudes
    PARAMETER (nlev = 5) ! Number of levels
    PARAMETER (nts = 3) ! Number of time steps

13  INTEGER gridID, zaxisID1, zaxisID2, taxisID, tsID
    INTEGER vlistID1, vlistID2, varID1, varID2, streamID1, streamID2

```

```

INTEGER i, nmiss, status, vdate, vtime
REAL*8 var1(nlon*nlat), var2(nlon*nlat*nlev)

18  !   Open the input dataset
    streamID1 = streamOpenRead("example.nc")
    IF ( streamID1 < 0 ) THEN
        WRITE(0,*) cdiStringError(streamID1)
        STOP
23  END IF

    !   Get the variable list of the dataset
    vlistID1 = streamInqVlist(streamID1)

28  !   Set the variable IDs
    varID1 = 0
    varID2 = 1

    !   Get the Time axis from the variable list
33  taxisID = vlistInqTaxis(vlistID1)

    !   Open the output dataset (GRIB format)
    streamID2 = streamOpenWrite("example.grb", FILETYPE_GRB)
    IF ( streamID2 < 0 ) THEN
38  WRITE(0,*) cdiStringError(streamID2)
        STOP
    END IF

    vlistID2 = vlistDuplicate(vlistID1)
43  CALL streamDefVlist(streamID2, vlistID2)

    !   Loop over the number of time steps
    DO tsID = 0, nts-1
48  !   Inquire the input time step */
        status = streamInqTimestep(streamID1, tsID)

        !   Get the verification date and time
        vdate = taxisInqVdate(taxisID)
53  vtime = taxisInqVtime(taxisID)

        !   Define the output time step
        status = streamDefTimestep(streamID2, tsID)

58  !   Read var1 and var2
        CALL streamReadVar(streamID1, varID1, var1, nmiss)
        CALL streamReadVar(streamID1, varID2, var2, nmiss)

        !   Write var1 and var2
63  CALL streamWriteVar(streamID2, varID1, var1, nmiss)
        CALL streamWriteVar(streamID2, varID2, var2, nmiss)
    END DO

    !   Close the streams
68  CALL streamClose(streamID1)
    CALL streamClose(streamID2)

END

```

B.4. Fortran 2003: mo_cdi and iso_c_binding

This is the Fortran 2003 version of the reading and writing examples above. The main difference to `cfortran.h` is the character handling. Here `CHARACTER(type=c_char)` is used instead of `CHARACTER`. Additionally plain fortran characters and character variables have to be converted to C characters by

- appending `'\0'` with `//C_NULL_CHAR`
- prepending `C_CHAR_` to plain characters
- take `ctrim` from `mo_cdi` for `CHARACTER(type=c_char)` variables

```

PROGRAM CDIREADF2003
  use iso_c_binding
  use mo_cdi

4  IMPLICIT NONE

  INTEGER :: gsize, nlevel, nvars, code
  INTEGER :: vdate, vtime, nmiss, status, ilev
9  INTEGER :: streamID, varID, gridID, zaxisID
  INTEGER :: tsID, vlistID, taxisID
  DOUBLE PRECISION, ALLOCATABLE :: field(:, :)
  CHARACTER(kind=c_char, len=256) :: name, longname, units

14  ! Open the dataset
  streamID = streamOpenRead(C_CHAR_"example.nc"//C_NULL_CHAR)
  IF ( streamID < 0 ) THEN
    PRINT *, 'Could not Read the file.'
    WRITE(0, *) cdiStringError(streamID)
19  STOP
  END IF

  ! Get the variable list of the dataset
  vlistID = streamInqVlist(streamID)
24
  nvars = vlistNvars(vlistID)

  DO varID = 0, nvars-1
    code = vlistInqVarCode(vlistID, varID)
29  CALL vlistInqVarName(vlistID, varID, name)
    CALL vlistInqVarLongname(vlistID, varID, longname)
    CALL vlistInqVarUnits(vlistID, varID, units)

    CALL ctrim(name)
34  CALL ctrim(longname)
    CALL ctrim(units)

    WRITE(*, *) 'Parameter: ', varID+1, code, ' ', trim(name), ' ', &
      trim(longname), ' ', trim(units), ' |'
39
  END DO

  ! Get the Time axis from the variable list
44  taxisID = vlistInqTaxis(vlistID)

```

```

! Loop over the time steps
DO tsID = 0, 999999
  ! Read the time step
  status = streamInqTimestep(streamID, tsID)
49  IF ( status == 0 ) exit

  ! Get the verification date and time
  vdate = taxisInqVdate(taxisID)
  vtime = taxisInqVtime(taxisID)
54

  WRITE(*,*) 'Timestep: ', tsID+1, vdate, vtime

  ! Read the variables at the current timestep
  DO varID = 0, nvars-1
    gridID = vlistInqVarGrid(vlistID, varID)
    gsize = gridInqSize(gridID)
    zaxisID = vlistInqVarZaxis(vlistID, varID)
    nlevel = zaxisInqSize(zaxisID)
    ALLOCATE(field(gsize, nlevel))
64    CALL streamReadVar(streamID, varID, field, nmiss)
    DO ilev = 1, nlevel
      WRITE(*,*) ' var=', varID+1, ' level=', ilev, ':', &
        MINVAL(field(:,ilev)), MAXVAL(field(:,ilev))
    END DO
69    DEALLOCATE(field)
  END DO
END DO

! Close the input stream
74 CALL streamClose(streamID)

END PROGRAM CDIREADF2003

```

PROGRAM CDIWRITEF2003

```

USE iso_c_binding
4 USE mo_cdi

```

```

IMPLICIT NONE

```

```

INTEGER nlon, nlat, nlev, nts
9 PARAMETER (nlon = 12) ! Number of longitudes
PARAMETER (nlat = 6) ! Number of latitudes
PARAMETER (nlev = 5) ! Number of levels
PARAMETER (nts = 3) ! Number of time steps

```

```

14 INTEGER gridID, zaxisID1, zaxisID2, taxisID
INTEGER vlistID, varID1, varID2, streamID, tsID
INTEGER i, nmiss, status
DOUBLE PRECISION lons(nlon), lats(nlat), levs(nlev)
DOUBLE PRECISION var1(nlon*nlat), var2(nlon*nlat*nlev)
19 CHARACTER(len=256) :: varname

```

```

DATA lons /0, 30, 60, 90, 120, 150, 180, 210, 240, 270, 300, 330/
DATA lats /-75, -45, -15, 15, 45, 75/
24 DATA levs /101300, 92500, 85000, 50000, 20000/

```

```

nmiss = 0

!   Create a regular lon/lat grid
gridID = gridCreate(GRID_LONLAT, nlon*nlat)
29  CALL gridDefXsize(gridID, nlon)
    CALL gridDefYsize(gridID, nlat)
    CALL gridDefXvals(gridID, lons)
    CALL gridDefYvals(gridID, lats)

34  !   Create a surface level Z-axis
    zaxisID1 = zaxisCreate(ZAXIS_SURFACE, 1)

!   Create a pressure level Z-axis
39  zaxisID2 = zaxisCreate(ZAXIS_PRESSURE, nlev)
    CALL zaxisDefLevels(zaxisID2, levs)

!   Create a variable list
    vlistID = vlistCreate()

44  !   Define the variables
    varID1 = vlistDefVar(vlistID, gridID, zaxisID1, TIME_VARIABLE)
    varID2 = vlistDefVar(vlistID, gridID, zaxisID2, TIME_VARIABLE)

!   Define the variable names
49  varname = "varname1"
    CALL vlistDefVarName(vlistID, varID1, TRIM(varname)//C_NULL_CHAR)
    CALL vlistDefVarName(vlistID, varID2, C_CHAR_"varname2"//C_NULL_CHAR)

!   Create a Time axis
54  taxisID = taxisCreate(TAXIS_ABSOLUTE)

!   Assign the Time axis to the variable list
    CALL vlistDefTaxis(vlistID, taxisID)

59  !   Create a dataset in netCDF fromat
    streamID = streamOpenWrite(C_CHAR_"example.nc"//C_NULL_CHAR, FILETYPE_NC)
    IF ( streamID < 0 ) THEN
        WRITE(0,*) cdiStringError(streamID)
        STOP
64  END IF

!   Assign the variable list to the dataset
    CALL streamDefVlist(streamID, vlistID)

69  !   Loop over the number of time steps
    DO tsID = 0, nts-1
!       Set the verification date to 1985-01-01 + tsID
        CALL taxisDefVdate(taxisID, 19850101+tsID)
!       Set the verification time to 12:00:00
74  CALL taxisDefVtime(taxisID, 120000)
!       Define the time step
        status = streamDefTimestep(streamID, tsID)

!       Init var1 and var2
79  DO i = 1, nlon*nlat
        var1(i) = 1.1
    END DO

```

```
      DO i = 1, nlon*nlat*nlev
        var2(i) = 2.2
84      END DO

!      Write var1 and var2
      CALL streamWriteVar(streamID, varID1, var1, nmiss)
      CALL streamWriteVar(streamID, varID2, var2, nmiss)
89      END DO

!      Close the output stream
      CALL streamClose(streamID)

94 !      Destroy the objects
      CALL vlistDestroy(vlistID)
      CALL taxisDestroy(taxisID)
      CALL zaxisDestroy(zaxisID1)
      CALL zaxisDestroy(zaxisID2)
99      CALL gridDestroy(gridID)

      END PROGRAM CDIWRITEF2003
```

Function index

G

gridCreate	31
gridDefXbounds	34
gridDefXlongname	36
gridDefXname	35
gridDefXsize	32
gridDefXunits	36
gridDefXvals	33
gridDefYbounds	35
gridDefYlongname	37
gridDefYname	37
gridDefYsize	33
gridDefYunits	38
gridDefYvals	34
gridDestroy	32
gridDuplicate	32
gridInqSize	32
gridInqType	32
gridInqXbounds	35
gridInqXlongname	36
gridInqXname	36
gridInqXsize	33
gridInqXunits	37
gridInqXvals	34
gridInqYbounds	35
gridInqYlongname	38
gridInqYname	37
gridInqYsize	33
gridInqYunits	38
gridInqYvals	34

S

streamClose	15
streamDefByteorder	15
streamDefTimestep	16
streamDefVlist	16
streamInqByteorder	15
streamInqFiletype	15
streamInqTimestep	16
streamInqVlist	16
streamOpenRead	14
streamOpenWrite	13
streamReadVar	17

streamReadVarSlice	17
streamWriteVar	17
streamWriteVarSlice	17

T

taxisCreate	43
taxisDefCalendar	45
taxisDefRdate	44
taxisDefRtime	44
taxisDefVdate	45
taxisDefVtime	45
taxisDestroy	44
taxisInqCalendar	46
taxisInqRdate	44
taxisInqRtime	44
taxisInqVdate	45
taxisInqVtime	45

V

vlistCat	20
vlistCopy	19
vlistCopyFlag	20
vlistCreate	19
vlistDefAttFlt	29
vlistDefAttInt	28
vlistDefAttTxt	30
vlistDefTaxis	21
vlistDefVar	22
vlistDefVarCode	23
vlistDefVarDatatype	26
vlistDefVarLongname	24
vlistDefVarMissval	27
vlistDefVarName	24
vlistDefVarStdname	25
vlistDefVarUnits	25
vlistDestroy	19
vlistDuplicate	19
vlistInqAtt	28
vlistInqAttFlt	29
vlistInqAttInt	29
vlistInqAttTxt	30
vlistInqNatts	28
vlistInqTaxis	21

vlistInqVarCode	23
vlistInqVarDatatype	26
vlistInqVarGrid	23
vlistInqVarLongname	24
vlistInqVarMissval	27
vlistInqVarName	24
vlistInqVarStdname	25
vlistInqVarUnits	26
vlistInqVarZaxis	23
vlistNgrids	20
vlistNvars	20
vlistNzaxis	20

Z

zaxisCreate	39
zaxisDefLevels	40
zaxisDefLongname	42
zaxisDefName	41
zaxisDefUnits	42
zaxisDestroy	40
zaxisInqLevel	41
zaxisInqLevels	40
zaxisInqLongname	42
zaxisInqName	41
zaxisInqSize	40
zaxisInqType	40
zaxisInqUnits	42