

CDI C Manual

Climate Data Interface
Version 1.6.0
March 2013

Uwe Schulzweida
Max-Planck-Institute for Meteorology

Contents

1. Introduction	5
1.1. Building from sources	5
1.1.1. Compilation	5
1.1.2. Installation	6
2. File Formats	7
2.1. GRIB	7
2.1.1. GRIB edition 1	8
2.1.2. GRIB edition 2	8
2.2. NetCDF	8
2.3. SERVICE	9
2.4. EXTRA	9
2.5. IEG	10
3. Use of the CDI Library	11
3.1. Creating a dataset	11
3.2. Reading a dataset	11
3.3. Compiling and Linking with the CDI library	12
4. CDI modules	13
4.1. Dataset functions	13
4.1.1. Create a new dataset: <code>streamOpenWrite</code>	13
4.1.2. Open a dataset for reading: <code>streamOpenRead</code>	14
4.1.3. Close an open dataset: <code>streamClose</code>	15
4.1.4. Get the filetype: <code>streamInqFiletype</code>	15
4.1.5. Define the byte order: <code>streamDefByteorder</code>	15
4.1.6. Get the byte order: <code>streamInqByteorder</code>	15
4.1.7. Define the variable list: <code>streamDefVlist</code>	16
4.1.8. Get the variable list: <code>streamInqVlist</code>	16
4.1.9. Define time step: <code>streamDefTimestep</code>	16
4.1.10. Get time step: <code>streamInqTimestep</code>	16
4.1.11. Write a variable: <code>streamWriteVar</code>	17
4.1.12. Write a variable: <code>streamWriteVarF</code>	17
4.1.13. Read a variable: <code>streamReadVar</code>	17
4.1.14. Write a horizontal slice of a variable: <code>streamWriteVarSlice</code>	17
4.1.15. Write a horizontal slice of a variable: <code>streamWriteVarSliceF</code>	18
4.1.16. Read a horizontal slice of a variable: <code>streamReadVarSlice</code>	18
4.2. Variable list functions	19
4.2.1. Create a variable list: <code>vlistCreate</code>	19
4.2.2. Destroy a variable list: <code>vlistDestroy</code>	19
4.2.3. Copy a variable list: <code>vlistCopy</code>	19
4.2.4. Duplicate a variable list: <code>vlistDuplicate</code>	19
4.2.5. Concatenate two variable lists: <code>vlistCat</code>	20
4.2.6. Copy some entries of a variable list: <code>vlistCopyFlag</code>	20

4.2.7.	Number of variables in a variable list: <code>vlistNvars</code>	20
4.2.8.	Number of grids in a variable list: <code>vlistNgrids</code>	20
4.2.9.	Number of zaxis in a variable list: <code>vlistNzaxis</code>	20
4.2.10.	Define the time axis: <code>vlistDefTaxis</code>	21
4.2.11.	Get the time axis: <code>vlistInqTaxis</code>	21
4.3.	Variable functions	22
4.3.1.	Define a Variable: <code>vlistDefVar</code>	22
4.3.2.	Get the Grid ID of a Variable: <code>vlistInqVarGrid</code>	23
4.3.3.	Get the Zaxis ID of a Variable: <code>vlistInqVarZaxis</code>	23
4.3.4.	Define the code number of a Variable: <code>vlistDefVarCode</code>	23
4.3.5.	Get the Code number of a Variable: <code>vlistInqVarCode</code>	23
4.3.6.	Define the name of a Variable: <code>vlistDefVarName</code>	24
4.3.7.	Get the name of a Variable: <code>vlistInqVarName</code>	24
4.3.8.	Define the long name of a Variable: <code>vlistDefVarLongname</code>	24
4.3.9.	Get the longname of a Variable: <code>vlistInqVarLongname</code>	24
4.3.10.	Define the standard name of a Variable: <code>vlistDefVarStdname</code>	25
4.3.11.	Get the standard name of a Variable: <code>vlistInqVarStdname</code>	25
4.3.12.	Define the units of a Variable: <code>vlistDefVarUnits</code>	25
4.3.13.	Get the units of a Variable: <code>vlistInqVarUnits</code>	25
4.3.14.	Define the data type of a Variable: <code>vlistDefVarDatatype</code>	26
4.3.15.	Get the data type of a Variable: <code>vlistInqVarDatatype</code>	26
4.3.16.	Define the missing value of a Variable: <code>vlistDefVarMissval</code>	26
4.3.17.	Get the missing value of a Variable: <code>vlistInqVarMissval</code>	27
4.4.	Attributes	28
4.4.1.	Get number of variable attributes: <code>vlistInqNatts</code>	28
4.4.2.	Get information about an attribute: <code>vlistInqAtt</code>	28
4.4.3.	Define an integer attribute: <code>vlistDefAttInt</code>	28
4.4.4.	Get the value(s) of an integer attribute: <code>vlistInqAttInt</code>	29
4.4.5.	Define a floating point attribute: <code>vlistDefAttFlt</code>	29
4.4.6.	Get the value(s) of a floating point attribute: <code>vlistInqAttFlt</code>	29
4.4.7.	Define a text attribute: <code>vlistDefAttTxt</code>	30
4.4.8.	Get the value(s) of a text attribute: <code>vlistInqAttTxt</code>	30
4.5.	Grid functions	31
4.5.1.	Create a horizontal Grid: <code>gridCreate</code>	31
4.5.2.	Destroy a horizontal Grid: <code>gridDestroy</code>	32
4.5.3.	Duplicate a horizontal Grid: <code>gridDuplicate</code>	32
4.5.4.	Get the type of a Grid: <code>gridInqType</code>	32
4.5.5.	Get the size of a Grid: <code>gridInqSize</code>	32
4.5.6.	Define the number of values of a X-axis: <code>gridDefXsize</code>	32
4.5.7.	Get the number of values of a X-axis: <code>gridInqXsize</code>	33
4.5.8.	Define the number of values of a Y-axis: <code>gridDefYsize</code>	33
4.5.9.	Get the number of values of a Y-axis: <code>gridInqYsize</code>	33
4.5.10.	Define the number of parallels between a pole and the equator: <code>gridDefNP</code>	33
4.5.11.	Get the number of parallels between a pole and the equator: <code>gridInqNP</code>	34
4.5.12.	Define the values of a X-axis: <code>gridDefXvals</code>	34
4.5.13.	Get all values of a X-axis: <code>gridInqXvals</code>	34
4.5.14.	Define the values of a Y-axis: <code>gridDefYvals</code>	34
4.5.15.	Get all values of a Y-axis: <code>gridInqYvals</code>	35
4.5.16.	Define the bounds of a X-axis: <code>gridDefXbounds</code>	35
4.5.17.	Get the bounds of a X-axis: <code>gridInqXbounds</code>	35
4.5.18.	Define the bounds of a Y-axis: <code>gridDefYbounds</code>	35

4.5.19. Get the bounds of a Y-axis: <code>gridInqYbounds</code>	36
4.5.20. Define the name of a X-axis: <code>gridDefXname</code>	36
4.5.21. Get the name of a X-axis: <code>gridInqXname</code>	36
4.5.22. Define the longname of a X-axis: <code>gridDefXlongname</code>	36
4.5.23. Get the longname of a X-axis: <code>gridInqXlongname</code>	37
4.5.24. Define the units of a X-axis: <code>gridDefXunits</code>	37
4.5.25. Get the units of a X-axis: <code>gridInqXunits</code>	37
4.5.26. Define the name of a Y-axis: <code>gridDefYname</code>	37
4.5.27. Get the name of a Y-axis: <code>gridInqYname</code>	38
4.5.28. Define the longname of a Y-axis: <code>gridDefYlongname</code>	38
4.5.29. Get the longname of a Y-axis: <code>gridInqYlongname</code>	38
4.5.30. Define the units of a Y-axis: <code>gridDefYunits</code>	38
4.5.31. Get the units of a Y-axis: <code>gridInqYunits</code>	39
4.6. Z-axis functions	40
4.6.1. Create a vertical Z-axis: <code>zaxisCreate</code>	40
4.6.2. Destroy a vertical Z-axis: <code>zaxisDestroy</code>	41
4.6.3. Get the type of a Z-axis: <code>zaxisInqType</code>	41
4.6.4. Get the size of a Z-axis: <code>zaxisInqSize</code>	41
4.6.5. Define the levels of a Z-axis: <code>zaxisDefLevels</code>	41
4.6.6. Get all levels of a Z-axis: <code>zaxisInqLevels</code>	42
4.6.7. Get one level of a Z-axis: <code>zaxisInqLevel</code>	42
4.6.8. Define the name of a Z-axis: <code>zaxisDefName</code>	42
4.6.9. Get the name of a Z-axis: <code>zaxisInqName</code>	42
4.6.10. Define the longname of a Z-axis: <code>zaxisDefLongname</code>	43
4.6.11. Get the longname of a Z-axis: <code>zaxisInqLongname</code>	43
4.6.12. Define the units of a Z-axis: <code>zaxisDefUnits</code>	43
4.6.13. Get the units of a Z-axis: <code>zaxisInqUnits</code>	43
4.7. T-axis functions	45
4.7.1. Create a Time axis: <code>taxisCreate</code>	45
4.7.2. Destroy a Time axis: <code>taxisDestroy</code>	46
4.7.3. Define the reference date: <code>taxisDefRdate</code>	46
4.7.4. Get the reference date: <code>taxisInqRdate</code>	46
4.7.5. Define the reference time: <code>taxisDefRtime</code>	46
4.7.6. Get the reference time: <code>taxisInqRtime</code>	46
4.7.7. Define the verification date: <code>taxisDefVdate</code>	47
4.7.8. Get the verification date: <code>taxisInqVdate</code>	47
4.7.9. Define the verification time: <code>taxisDefVtime</code>	47
4.7.10. Get the verification time: <code>taxisInqVtime</code>	47
4.7.11. Define the calendar: <code>taxisDefCalendar</code>	47
4.7.12. Get the calendar: <code>taxisInqCalendar</code>	48
A. Quick Reference	50
B. Examples	64
B.1. Write a dataset	64
B.1.1. Result	65
B.2. Read a dataset	66
B.3. Copy a dataset	67
Function index	70

1. Introduction

CDI is an Interface to access Climate and NWP model Data. The interface is independent from a specific data format and has a C and Fortran API. **CDI** was developed for a fast and machine independent access to GRIB and netCDF datasets with the same interface. The local [MPI-MET](#) data formats SERVICE, EXTRA and IEG are also supported.

1.1. Building from sources

This section describes how to build the **CDI** library from the sources on a UNIX system. **CDI** is using the GNU configure and build system to compile the source code. The only requirement is a working ANSI C99 compiler.

First go to the [download](#) page (<http://code.zmaw.de/projects/cdi/files>) to get the latest distribution, if you do not already have it.

To take full advantage of **CDI**'s features the following additional libraries should be installed:

- Unidata [netCDF](#) library (<http://www.unidata.ucar.edu/packages/netcdf>) version 3 or higher. This is needed to read/write netCDF files with **CDI**.
- The ECMWF [GRIB_API](#) (http://www.ecmwf.int/products/data/software/grib_api.html) version 1.9.5 or higher. This library is needed to encode/decode GRIB2 records with **CDI**.

1.1.1. Compilation

Compilation is now done by performing the following steps:

1. Unpack the archive, if you haven't already done that:

```
gunzip cdi-$VERSION.tar.gz      # uncompress the archive
tar xf cdi-$VERSION.tar         # unpack it
cd cdi-$VERSION
```

2. Run the configure script:

```
./configure
```

Or optionally with netCDF support:

```
./configure --with-netcdf=<netCDF root directory>
```

For an overview of other configuration options use

```
./configure --help
```

3. Compile the program by running make:

```
make
```

The software should compile without problems and the **CDI** library (`libcdi.a`) should be available in the `src` directory of the distribution.

1.1.2. Installation

After the compilation of the source code do a `make install`, possibly as root if the destination permissions require that.

```
make install
```

The library is installed into the directory `<prefix>/lib`. The C and Fortran include files are installed into the directory `<prefix>/include`. `<prefix>` defaults to `/usr/local` but can be changed with the `--prefix` option of the configure script.

2. File Formats

2.1. GRIB

GRIB [\[GRIB\]](#) (GRIdded Binary) is a standard format designed by the World Meteorological Organization (WMO) to support the efficient transmission and storage of gridded meteorological data.

A GRIB record consists of a series of header sections, followed by a bitstream of packed data representing one horizontal grid of data values. The header sections are intended to fully describe the data included in the bitstream, specifying information such as the parameter, units, and precision of the data, the grid system and level type on which the data is provided, and the date and time for which the data are valid.

Non-numeric descriptors are enumerated in tables, such that a 1-byte code in a header section refers to a unique description. The WMO provides a standard set of enumerated parameter names and level types, but the standard also allows for the definition of locally used parameters and geometries. Any activity that generates and distributes GRIB records must also make their locally defined GRIB tables available to users.

CDI does not support the full GRIB standard. The following data representation and level types are implemented:

GRIB1 grid type	GRIB2 template	GRIB_API name	description
0	3.0	regular_ll	Regular longitude/latitude grid
3	–	lambert	Lambert conformal grid
4	3.40	regular_gg	Regular Gaussian longitude/latitude grid
4	3.40	reduced_gg	Reduced Gaussian longitude/latitude grid
10	3.1	rotated_ll	Rotated longitude/latitude grid
50	3.50	sh	Spherical harmonic coefficients
192	3.100	–	Icosahedral-hexagonal GME grid
–	3.101	–	General unstructured grid

GRIB1 level type	GRIB2 level type	GRIB_API name	description
1	1	surface	Surface level
2	2	cloudBase	Cloud base level
3	3	cloudTop	Level of cloud tops
4	4	isothermZero	Level of 0° C isotherm
8	8	nominalTop	Norminal top of atmosphere
9	9	seaBottom	Sea bottom
10	10	entireAtmosphere	Entire atmosphere
99	–	–	Isobaric level in Pa
100	100	isobaricInhPa	Isobaric level in hPa
102	101	meanSea	Mean sea level
103	102	heightAboveSea	Altitude above mean sea level
105	103	heightAboveGround	Height level above ground
107	104	sigma	Sigma level
109	105	hybrid	Hybrid level
110	105	hybridLayer	Layer between two hybrid levels
111	106	depthBelowLand	Depth below land surface
112	106	depthBelowLandLayer	Layer between two depths below land surface
113	107	theta	Isentropic (theta) level
160	160	depthBelowSea	Depth below sea level

2.1.1. GRIB edition 1

GRIB1 is implemented in **CDI** as an internal library and enabled per default. The internal GRIB1 library is called CGRIBEX. This is lightweight version of the ECMWF GRIBEX library. CGRIBEX is written in ANSI C with a portable Fortran interface. The configure option `--disable-cgribex` will disable the encoding/decoding of GRIB1 records with CGRIBEX.

2.1.2. GRIB edition 2

GRIB2 is available in **CDI** via the ECMWF GRIB_API [[GRIBAPI](#)]. GRIB_API is an external library and not part of **CDI**. To use GRIB2 with **CDI** the GRIB_API library must be installed before the configuration of the **CDI** library. Use the configure option `--with-grib.api` to enable GRIB2 support.

The GRIB_API library is also used to encode/decode GRIB1 records if the support for the CGRIBEX library is disabled.

2.2. NetCDF

NetCDF [[NetCDF](#)] (Network Common Data Form) is an interface for array-oriented data access and a library that provides an implementation of the interface. The netCDF library also defines a machine-independent format for representing scientific data. Together, the interface, library, and format support the creation, access, and sharing of scientific data.

CDI only supports the classic data model of netCDF and arrays up to 4 dimensions. These dimensions should only be used by the horizontal and vertical grid and the time. The netCDF attributes should follow the [GDT](#), [COARDS](#) or [CF Conventions](#).

NetCDF is an external library and not part of **CDI**. To use netCDF with **CDI** the netCDF library must be installed before the configuration of the **CDI** library. Use the configure option `--with-netcdf` to enable netCDF support (see [Build](#)).

2.3. SERVICE

SERVICE is the binary exchange format of the atmospheric general circulation model ECHAM [ECHAM]. It has a header section with 8 integer values followed by the data section. The header and the data section have the standard Fortran blocking for binary data records. A SERVICE record can have an accuracy of 4 or 8 bytes and the byteorder can be little or big endian. In **CDI** the accuracy of the header and data section must be the same. The following Fortran code example can be used to read a SERVICE record with an accuracy of 4 bytes:

```
INTEGER*4 icode,ilevel,ideate,itime,nlon,nlat,idispo1,idispo2
REAL*4 field(mlon,mlat)
...
READ(unit) icode,ilevel,ideate,itime,nlon,nlat,idispo1,idispo2
READ(unit) ((field(ilon,ilat), ilon=1,nlon), ilat=1,nlat)
```

The constants `mlon` and `mlat` must be greater or equal than `nlon` and `nlat`. The meaning of the variables are:

<code>icode</code>	The code number
<code>ilevel</code>	The level
<code>ideate</code>	The date as YYYYMMDD
<code>itime</code>	The time as hhmmss
<code>nlon</code>	The number of longitudes
<code>nlat</code>	The number of latitudes
<code>idispo1</code>	For the users disposal (Not used in CDI)
<code>idispo2</code>	For the users disposal (Not used in CDI)

SERVICE is implemented in **CDI** as an internal library and enabled per default. The configure option `--disable-service` will disable the support for the SERVICE format.

2.4. EXTRA

EXTRA is the standard binary output format of the ocean model MPIOM [MPIOM]. It has a header section with 4 integer values followed by the data section. The header and the data section have the standard Fortran blocking for binary data records. An EXTRA record can have an accuracy of 4 or 8 bytes and the byteorder can be little or big endian. In **CDI** the accuracy of the header and data section must be the same. The following Fortran code example can be used to read an EXTRA record with an accuracy of 4 bytes:

```
INTEGER*4 ideate,icode,ilevel,nsiz
REAL*4 field(msiz)
...
READ(unit) ideate,icode,ilevel,nsiz
READ(unit) (field(isiz),isiz=1,nsiz)
```

The constant `msiz` must be greater or equal than `nsiz`. The meaning of the variables are:

<code>ideate</code>	The date as YYYYMMDD
<code>icode</code>	The code number
<code>ilevel</code>	The level
<code>nsiz</code>	The size of the field

EXTRA is implemented in **CDI** as an internal library and enabled per default. The configure option `--disable-extra` will disable the support for the EXTRA format.

2.5. IEG

IEG is the standard binary output format of the regional model REMO [[REMO](#)]. It is simple an unpacked GRIB edition 1 format. The product and grid description sections are coded with 4 byte integer values and the data section can have 4 or 8 byte IEEE floating point values. The header and the data section have the standard Fortran blocking for binary data records. The IEG format has a fixed size of 100 for the vertical coordinate table. That means it is not possible to store more than 50 model levels with this format. **CDI** supports only data on Gaussian and LonLat grids for the IEG format.

IEG is implemented in **CDI** as an internal library and enabled per default. The configure option `--disable-ieg` will disable the support for the IEG format.

3. Use of the CDI Library

This chapter provides templates of common sequences of **CDI** calls needed for common uses. For clarity only the names of routines are used. Declarations and error checking were omitted. Statements that are typically invoked multiple times were indented and ... is used to represent arbitrary sequences of other statements. Full parameter lists are described in later chapters. Complete examples for write, read and copy a dataset with **CDI** can be found in [Appendix B](#).

3.1. Creating a dataset

Here is a typical sequence of **CDI** calls used to create a new dataset:

```
gridCreate      ! create a horizontal Grid: from type and size
...
zaxisCreate     ! create a vertical Z-axis: from type and size
...
taxisCreate     ! create a Time axis: from type
...
vlistCreate     ! create a variable list
...
    vlistDefVar  ! define variables: from Grid and Z-axis
...
streamOpenWrite ! create a dataset: from name and file type
...
streamDefVlist  ! define variable list
...
streamDefTimestep ! define time step
...
    streamWriteVar ! write variable
...
streamClose     ! close the dataset
...
vlistDestroy    ! destroy the variable list
...
taxisDestroy    ! destroy the Time axis
...
zaxisDestroy    ! destroy the Z-axis
...
gridDestroy     ! destroy the Grid
```

3.2. Reading a dataset

Here is a typical sequence of **CDI** calls used to read a dataset:

```
streamOpenRead  ! open existing dataset
...
streamInqVlist  ! find out what is in it
...
    vlistInqVarGrid ! get an identifier to the Grid
...
```

```

    vlistInqVarZaxis ! get an identifier to the Z-axis
    ...
    vlistInqTaxis    ! get an identifier to the T-axis
    ...
    streamInqTimestep ! get time step
    ...
    streamReadVar     ! read variable
    ...
    streamClose       ! close the dataset

```

3.3. Compiling and Linking with the CDI library

Details of how to compile and link a program that uses the **CDI** C or FORTRAN interfaces differ, depending on the operating system, the available compilers, and where the **CDI** library and include files are installed. Here are examples of how to compile and link a program that uses the **CDI** library on a Unix platform, so that you can adjust these examples to fit your installation. Every C file that references **CDI** functions or constants must contain an appropriate `include` statement before the first such reference:

```
#include "cdi.h"
```

Unless the `cdi.h` file is installed in a standard directory where C compiler always looks, you must use the `-I` option when invoking the compiler, to specify a directory where `cdi.h` is installed, for example:

```
cc -c -I/usr/local/cdi/include myprogram.c
```

Alternatively, you could specify an absolute path name in the `include` statement, but then your program would not compile on another platform where **CDI** is installed in a different location. Unless the **CDI** library is installed in a standard directory where the linker always looks, you must use the `-L` and `-l` options to link an object file that uses the **CDI** library. For example:

```
cc -o myprogram myprogram.o -L/usr/local/cdi/lib -lcdi -lm
```

Alternatively, you could specify an absolute path name for the library:

```
cc -o myprogram myprogram.o -L/usr/local/cdi/lib/libcdi -lm
```

If the **CDI** library is using other external libraries, you must add this libraries in the same way. For example with the netCDF library:

```
cc -o myprogram myprogram.o -L/usr/local/cdi/lib -lcdi -lm \
    -L/usr/local/netcdf/lib -lnetcdf
```

4. CDI modules

4.1. Dataset functions

This module contains functions to read and write the data. To create a new dataset the output format must be specified with one of the following predefined file format types:

FILETYPE_GRB	File type GRIB version 1
FILETYPE_GRB2	File type GRIB version 2
FILETYPE_NC	File type netCDF
FILETYPE_NC2	File type netCDF version 2 (64-bit)
FILETYPE_NC4	File type netCDF-4 (HDF5)
FILETYPE_NC4C	File type netCDF-4 classic
FILETYPE_SRV	File type SERVICE
FILETYPE_EXT	File type EXTRA
FILETYPE_IEG	File type IEG

FILETYPE_GRB2 is only available if the **CDI** library was compiled with GRIB_API support and all netCDF file types are only available if the **CDI** library was compiled with netCDF support!

To set the byte order of a binary dataset with the file format type FILETYPE_SRV, FILETYPE_EXT or FILETYPE_IEG use one of the following predefined constants in the call to [streamDefByteorder](#):

CDI_BIGENDIAN	Byte order big endian
CDI_LITTLEENDIAN	Byte order little endian

4.1.1. Create a new dataset: streamOpenWrite

The function `streamOpenWrite` creates a new dataset.

Usage

```
int streamOpenWrite(const char *path, int filetype);
```

<code>path</code>	The name of the new dataset.
<code>filetype</code>	The type of the file format, one of the set of predefined CDI file format types. The valid CDI file format types are FILETYPE_GRB, FILETYPE_GRB2, FILETYPE_NC, FILETYPE_NC2, FILETYPE_NC4, FILETYPE_NC4C, FILETYPE_SRV, FILETYPE_EXT and FILETYPE_IEG.

Result

Upon successful completion `streamOpenWrite` returns an identifier to the open stream. Otherwise, a negative number with the error status is returned.

Errors

CDI_ESYSTEM	Operating system error.
CDI_EINVAL	Invalid argument.
CDI_EUFILETYPE	Unsupported file type.
CDI_ELIBNAVAIL	Library support not compiled in.

Example

Here is an example using `streamOpenWrite` to create a new netCDF file named `foo.nc` for writing:

```
#include "cdi.h"
...
int streamID;
...
streamID = streamOpenWrite("foo.nc", FILETYPE_NC);
if ( streamID < 0 ) handle_error(streamID);
...
```

4.1.2. Open a dataset for reading: streamOpenRead

The function `streamOpenRead` opens an existing dataset for reading.

Usage

```
int streamOpenRead(const char *path);
```

`path` The name of the dataset to be read.

Result

Upon successful completion `streamOpenRead` returns an identifier to the open stream. Otherwise, a negative number with the error status is returned.

Errors

CDI_ESYSTEM	Operating system error.
CDI_EINVAL	Invalid argument.
CDI_EUFILETYPE	Unsupported file type.
CDI_ELIBNAVAIL	Library support not compiled in.

Example

Here is an example using `streamOpenRead` to open an existing netCDF file named `foo.nc` for reading:

```
#include "cdi.h"
...
int streamID;
...
streamID = streamOpenRead("foo.nc");
if ( streamID < 0 ) handle_error(streamID);
...
```

4.1.3. Close an open dataset: `streamClose`

The function `streamClose` closes an open dataset.

Usage

```
void streamClose(int streamID);
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

4.1.4. Get the filetype: `streamInqFiletype`

The function `streamInqFiletype` returns the filetype of a stream.

Usage

```
int streamInqFiletype(int streamID);
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

Result

`streamInqFiletype` returns the type of the file format, one of the set of predefined **CDI** file format types. The valid **CDI** file format types are `FILETYPE_GRB`, `FILETYPE_GRB2`, `FILETYPE_NC`, `FILETYPE_NC2`, `FILETYPE_NC4`, `FILETYPE_NC4C`, `FILETYPE_SRV`, `FILETYPE_EXT` and `FILETYPE_IEG`.

4.1.5. Define the byte order: `streamDefByteorder`

The function `streamDefByteorder` defines the byte order of a binary dataset with the file format type `FILETYPE_SRV`, `FILETYPE_EXT` or `FILETYPE_IEG`.

Usage

```
void streamDefByteorder(int streamID, int byteorder);
```

`streamID` Stream ID, from a previous call to [streamOpenWrite](#).

`byteorder` The byte order of a dataset, one of the **CDI** constants `CDI_BIGENDIAN` and `CDI_LITTLEENDIAN`.

4.1.6. Get the byte order: `streamInqByteorder`

The function `streamInqByteorder` returns the byte order of a binary dataset with the file format type `FILETYPE_SRV`, `FILETYPE_EXT` or `FILETYPE_IEG`.

Usage

```
int streamInqByteorder(int streamID);
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

Result

`streamInqByteorder` returns the type of the byte order. The valid **CDI** byte order types are `CDI_BIGENDIAN` and `CDI_LITTLEENDIAN`

4.1.7. Define the variable list: `streamDefVlist`

The function `streamDefVlist` defines the variable list of a stream.

Usage

```
void streamDefVlist(int streamID, int vlistID);
```

`streamID` Stream ID, from a previous call to [streamOpenWrite](#).

`vlistID` Variable list ID, from a previous call to [vlistCreate](#).

4.1.8. Get the variable list: `streamInqVlist`

The function `streamInqVlist` returns the variable list of a stream.

Usage

```
int streamInqVlist(int streamID);
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

Result

`streamInqVlist` returns an identifier to the variable list.

4.1.9. Define time step: `streamDefTimestep`

The function `streamDefTimestep` defines the time step of a stream.

Usage

```
int streamDefTimestep(int streamID, int tsID);
```

`streamID` Stream ID, from a previous call to [streamOpenWrite](#).

`tsID` Timestep identifier.

Result

`streamDefTimestep` returns the number of records of the time step.

4.1.10. Get time step: `streamInqTimestep`

The function `streamInqTimestep` returns the time step of a stream.

Usage

```
int streamInqTimestep(int streamID, int tsID);
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#) or [streamOpenWrite](#).

`tsID` Timestep identifier.

Result

`streamInqTimestep` returns the number of records of the time step.

4.1.11. Write a variable: streamWriteVar

The function `streamWriteVar` writes the values of one time step of a variable to an open dataset. The values are converted to the external data type of the variable, if necessary.

Usage

```
void streamWriteVar(int streamID, int varID, const double *data, int nmiss);
```

`streamID` Stream ID, from a previous call to [streamOpenWrite](#).
`varID` Variable identifier.
`data` Pointer to a block of double precision floating point data values to be written.
`nmiss` Number of missing values.

4.1.12. Write a variable: streamWriteVarF

The function `streamWriteVarF` writes the values of one time step of a variable to an open dataset. The values are converted to the external data type of the variable, if necessary. Only support for `netCDF` was implemented in this function.

Usage

```
void streamWriteVarF(int streamID, int varID, const float *data, int nmiss);
```

`streamID` Stream ID, from a previous call to [streamOpenWrite](#).
`varID` Variable identifier.
`data` Pointer to a block of single precision floating point data values to be written.
`nmiss` Number of missing values.

4.1.13. Read a variable: streamReadVar

The function `streamReadVar` reads all the values of one time step of a variable from an open dataset.

Usage

```
void streamReadVar(int streamID, int varID, double *data, int *nmiss);
```

`streamID` Stream ID, from a previous call to [streamOpenRead](#).
`varID` Variable identifier.
`data` Pointer to the location into which the data values are read. The caller must allocate space for the returned values.
`nmiss` Number of missing values.

4.1.14. Write a horizontal slice of a variable: streamWriteVarSlice

The function `streamWriteVarSlice` writes the values of a horizontal slice of a variable to an open dataset. The values are converted to the external data type of the variable, if necessary.

Usage

```
void streamWriteVarSlice(int streamID, int varID, int levelID, const double *data,
                        int nmiss);
```

streamID Stream ID, from a previous call to [streamOpenWrite](#).

varID Variable identifier.

levelID Level identifier.

data Pointer to a block of double precision floating point data values to be written.

nmiss Number of missing values.

4.1.15. Write a horizontal slice of a variable: streamWriteVarSliceF

The function `streamWriteVarSliceF` writes the values of a horizontal slice of a variable to an open dataset. The values are converted to the external data type of the variable, if necessary. Only support for netCDF was implemented in this function.

Usage

```
void streamWriteVarSliceF(int streamID, int varID, int levelID, const float *data,
                        int nmiss);
```

streamID Stream ID, from a previous call to [streamOpenWrite](#).

varID Variable identifier.

levelID Level identifier.

data Pointer to a block of single precision floating point data values to be written.

nmiss Number of missing values.

4.1.16. Read a horizontal slice of a variable: streamReadVarSlice

The function `streamReadVar` reads all the values of a horizontal slice of a variable from an open dataset.

Usage

```
void streamReadVarSlice(int streamID, int varID, int levelID, double *data,
                        int *nmiss);
```

streamID Stream ID, from a previous call to [streamOpenRead](#).

varID Variable identifier.

levelID Level identifier.

data Pointer to the location into which the data values are read. The caller must allocate space for the returned values.

nmiss Number of missing values.

4.2. Variable list functions

This module contains functions to handle a list of variables. A variable list is a collection of all variables of a dataset.

4.2.1. Create a variable list: `vlistCreate`

Usage

```
int vlistCreate(void);
```

Example

Here is an example using `vlistCreate` to create a variable list and add a variable with `vlistDefVar`.

```
#include "cdi.h"
...
int vlistID, varID;
...
vlistID = vlistCreate();
varID = vlistDefVar(vlistID, gridID, zaxisID, TSTEP_INSTANT);
...
streamDefVlist(streamID, vlistID);
...
vlistDestroy(vlistID);
...
```

4.2.2. Destroy a variable list: `vlistDestroy`

Usage

```
void vlistDestroy(int vlistID);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`

4.2.3. Copy a variable list: `vlistCopy`

The function `vlistCopy` copies all entries from `vlistID1` to `vlistID2`.

Usage

```
void vlistCopy(int vlistID2, int vlistID1);
```

`vlistID2` Target variable list ID

`vlistID1` Source variable list ID

4.2.4. Duplicate a variable list: `vlistDuplicate`

The function `vlistDuplicate` duplicates the variable list from `vlistID1`.

Usage

```
int vlistDuplicate(int vlistID);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`

Result

`vlistDuplicate` returns an identifier to the duplicated variable list.

4.2.5. Concatenate two variable lists: `vlistCat`

Concatenate the variable list `vlistID1` at the end of `vlistID2`.

Usage

```
void vlistCat(int vlistID2, int vlistID1);  
  
vlistID2  Target variable list ID  
vlistID1  Source variable list ID
```

4.2.6. Copy some entries of a variable list: `vlistCopyFlag`

The function `vlistCopyFlag` copies all entries with a flag from `vlistID1` to `vlistID2`.

Usage

```
void vlistCopyFlag(int vlistID2, int vlistID1);  
  
vlistID2  Target variable list ID  
vlistID1  Source variable list ID
```

4.2.7. Number of variables in a variable list: `vlistNvars`

The function `vlistNvars` returns the number of variables in the variable list `vlistID`.

Usage

```
int vlistNvars(int vlistID);  
  
vlistID  Variable list ID, from a previous call to vlistCreate
```

Result

`vlistNvars` returns the number of variables in a variable list.

4.2.8. Number of grids in a variable list: `vlistNgrids`

The function `vlistNgrids` returns the number of grids in the variable list `vlistID`.

Usage

```
int vlistNgrids(int vlistID);  
  
vlistID  Variable list ID, from a previous call to vlistCreate
```

Result

`vlistNgrids` returns the number of grids in a variable list.

4.2.9. Number of zaxis in a variable list: `vlistNzaxis`

The function `vlistNzaxis` returns the number of zaxis in the variable list `vlistID`.

Usage

```
int vlistNzaxis(int vlistID);
```

`vlistID` Variable list ID, from a previous call to [vlistCreate](#)

Result

`vlistNzaxis` returns the number of zaxis in a variable list.

4.2.10. Define the time axis: vlistDefTaxis

The function `vlistDefTaxis` defines the time axis of a variable list.

Usage

```
void vlistDefTaxis(int vlistID, int taxisID);
```

`vlistID` Variable list ID, from a previous call to [vlistCreate](#)

`taxisID` Time axis ID, from a previous call to [taxisCreate](#)

4.2.11. Get the time axis: vlistInqTaxis

The function `vlistInqTaxis` returns the time axis of a variable list.

Usage

```
int vlistInqTaxis(int vlistID);
```

`vlistID` Variable list ID, from a previous call to [vlistCreate](#)

Result

`vlistInqTaxis` returns an identifier to the time axis.

4.3. Variable functions

This module contains functions to add new variables to a variable list and to get information about variables from a variable list. To add new variables to a variables list one of the following time types must be specified:

<code>TIME_CONSTANT</code>	For time constant variables
<code>TIME_VARIABLE</code>	For time varying variables

The default data type is 16 bit for GRIB and 32 bit for all other file format types. To change the data type use one of the following predefined constants:

<code>DATATYPE_PACK8</code>	8 packed bit (only for GRIB)
<code>DATATYPE_PACK16</code>	16 packed bit (only for GRIB)
<code>DATATYPE_PACK24</code>	24 packed bit (only for GRIB)
<code>DATATYPE_FLT32</code>	32 bit floating point
<code>DATATYPE_FLT64</code>	64 bit floating point
<code>DATATYPE_INT8</code>	8 bit integer
<code>DATATYPE_INT16</code>	16 bit integer
<code>DATATYPE_INT32</code>	32 bit integer

4.3.1. Define a Variable: `vlistDefVar`

The function `vlistDefVar` adds a new variable to `vlistID`.

Usage

```
int vlistDefVar(int vlistID, int gridID, int zaxisID, int tsteptype);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`gridID` Grid ID, from a previous call to `gridCreate`.

`zaxisID` Z-axis ID, from a previous call to `zaxisCreate`.

`tsteptype` One of the set of predefined **CDI** timestep types. The valid **CDI** timestep types are `TSTEP_CONSTANT` and `TSTEP_INSTANT`.

Result

`vlistDefVar` returns an identifier to the new variable.

Example

Here is an example using `vlistCreate` to create a variable list and add a variable with `vlistDefVar`.

```
#include "cdi.h"
...
int vlistID, varID;
...
vlistID = vlistCreate();
varID = vlistDefVar(vlistID, gridID, zaxisID, TIME_INSTANT);
...
streamDefVlist(streamID, vlistID);
...
vlistDestroy(vlistID);
...
```

4.3.2. Get the Grid ID of a Variable: `vlistInqVarGrid`

The function `vlistInqVarGrid` returns the grid ID of a variable.

Usage

```
int vlistInqVarGrid(int vlistID, int varID);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

Result

`vlistInqVarGrid` returns the grid ID of the variable.

4.3.3. Get the Zaxis ID of a Variable: `vlistInqVarZaxis`

The function `vlistInqVarZaxis` returns the zaxis ID of a variable.

Usage

```
int vlistInqVarZaxis(int vlistID, int varID);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

Result

`vlistInqVarZaxis` returns the zaxis ID of the variable.

4.3.4. Define the code number of a Variable: `vlistDefVarCode`

The function `vlistDefVarCode` defines the code number of a variable.

Usage

```
void vlistDefVarCode(int vlistID, int varID, int code);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`code` Code number.

4.3.5. Get the Code number of a Variable: `vlistInqVarCode`

The function `vlistInqVarCode` returns the code number of a variable.

Usage

```
int vlistInqVarCode(int vlistID, int varID);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

Result

`vlistInqVarCode` returns the code number of the variable.

4.3.6. Define the name of a Variable: `vlistDefVarName`

The function `vlistDefVarName` defines the name of a variable.

Usage

```
void vlistDefVarName(int vlistID, int varID, const char *name);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.
`varID` Variable identifier.
`name` Name of the variable.

4.3.7. Get the name of a Variable: `vlistInqVarName`

The function `vlistInqVarName` returns the name of a variable.

Usage

```
void vlistInqVarName(int vlistID, int varID, char *name);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.
`varID` Variable identifier.
`name` Returned variable name. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the pre-defined constant `CDI_MAX_NAME`.

Result

`vlistInqVarName` returns the name of the variable to the parameter `name` if available, otherwise the result is an empty string.

4.3.8. Define the long name of a Variable: `vlistDefVarLongname`

The function `vlistDefVarLongname` defines the long name of a variable.

Usage

```
void vlistDefVarLongname(int vlistID, int varID, const char *longname);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.
`varID` Variable identifier.
`longname` Long name of the variable.

4.3.9. Get the longname of a Variable: `vlistInqVarLongname`

The function `vlistInqVarLongname` returns the longname of a variable if available, otherwise the result is an empty string.

Usage

```
void vlistInqVarLongname(int vlistID, int varID, char *longname);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.
`varID` Variable identifier.
`longname` Long name of the variable. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`vlistInqVaeLongname` returns the longname of the variable to the parameter `longname`.

4.3.10. Define the standard name of a Variable: `vlistDefVarStdname`

The function `vlistDefVarStdname` defines the standard name of a variable.

Usage

```
void vlistDefVarStdname(int vlistID, int varID, const char *stdname);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`stdname` Standard name of the variable.

4.3.11. Get the standard name of a Variable: `vlistInqVarStdname`

The function `vlistInqVarStdname` returns the standard name of a variable if available, otherwise the result is an empty string.

Usage

```
void vlistInqVarStdname(int vlistID, int varID, char *stdname);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`stdname` Standard name of the variable. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`vlistInqVarName` returns the standard name of the variable to the parameter `stdname`.

4.3.12. Define the units of a Variable: `vlistDefVarUnits`

The function `vlistDefVarUnits` defines the units of a variable.

Usage

```
void vlistDefVarUnits(int vlistID, int varID, const char *units);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.

`varID` Variable identifier.

`units` Units of the variable.

4.3.13. Get the units of a Variable: `vlistInqVarUnits`

The function `vlistInqVarUnits` returns the units of a variable if available, otherwise the result is an empty string.

Usage

```
void vlistInqVarUnits(int vlistID, int varID, char *units);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).

varID Variable identifier.

units Units of the variable. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`vlistInqVarUnits` returns the units of the variable to the parameter `units`.

4.3.14. Define the data type of a Variable: `vlistDefVarDatatype`

The function `vlistDefVarDatatype` defines the data type of a variable.

Usage

```
void vlistDefVarDatatype(int vlistID, int varID, int datatype);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).

varID Variable identifier.

datatype The data type identifier. The valid **CDI** data types are `DATATYPE_PACK8`, `DATATYPE_PACK16`, `DATATYPE_PACK24`, `DATATYPE_FLT32`, `DATATYPE_FLT64`, `DATATYPE_INT8`, `DATATYPE_INT16` and `DATATYPE_INT32`.

4.3.15. Get the data type of a Variable: `vlistInqVarDatatype`

The function `vlistInqVarDatatype` returns the data type of a variable.

Usage

```
int vlistInqVarDatatype(int vlistID, int varID);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).

varID Variable identifier.

Result

`vlistInqVarDatatype` returns an identifier to the data type of the variable. The valid **CDI** data types are `DATATYPE_PACK8`, `DATATYPE_PACK16`, `DATATYPE_PACK24`, `DATATYPE_FLT32`, `DATATYPE_FLT64`, `DATATYPE_INT8`, `DATATYPE_INT16` and `DATATYPE_INT32`.

4.3.16. Define the missing value of a Variable: `vlistDefVarMissval`

The function `vlistDefVarMissval` defines the missing value of a variable.

Usage

```
void vlistDefVarMissval(int vlistID, int varID, double missval);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).

varID Variable identifier.

missval Missing value.

4.3.17. Get the missing value of a Variable: vlistInqVarMissval

The function `vlistInqVarMissval` returns the missing value of a variable.

Usage

```
double vlistInqVarMissval(int vlistID, int varID);
```

`vlistID` Variable list ID, from a previous call to [vlistCreate](#).
`varID` Variable identifier.

Result

`vlistInqVarMissval` returns the missing value of the variable.

4.4. Attributes

Attributes may be associated with each variable to specify non CDI standard properties. CDI standard properties as code, name, units, and missing value are directly associated with each variable by the corresponding CDI function (e.g. `vlistDefVarName`). An attribute has a variable to which it is assigned, a name, a type, a length, and a sequence of one or more values. The attributes have to be defined after the variable is created and before the variable list is associated with a stream. Attributes are only used for netCDF datasets.

It is also possible to have attributes that are not associated with any variable. These are called global attributes and are identified by using `CDI_GLOBAL` as a variable pseudo-ID. Global attributes are usually related to the dataset as a whole.

CDI supports integer, floating point and text attributes. The data types are defined by the following predefined constants:

<code>DATATYPE_INT16</code>	16-bit integer attribute
<code>DATATYPE_INT32</code>	32-bit integer attribute
<code>DATATYPE_FLT32</code>	32-bit floating point attribute
<code>DATATYPE_FLT64</code>	64-bit floating point attribute
<code>DATATYPE_TXT</code>	Text attribute

4.4.1. Get number of variable attributes: `vlistInqNatts`

The function `vlistInqNatts` gets the number of variable attributes assigned to this variable.

Usage

```
int vlistInqNatts(int vlistID, int varID, int *nattsp);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.
`varID` Variable identifier, or `CDI_GLOBAL` for a global attribute.
`nattsp` Pointer to location for returned number of variable attributes.

4.4.2. Get information about an attribute: `vlistInqAtt`

The function `vlistInqAtt` gets information about an attribute.

Usage

```
int vlistInqAtt(int vlistID, int varID, int attnum, char *name, int *typep, int *lenp);
```

`vlistID` Variable list ID, from a previous call to `vlistCreate`.
`varID` Variable identifier, or `CDI_GLOBAL` for a global attribute.
`attnum` Attribute number (from 0 to `natts-1`).
`name` Pointer to the location for the returned attribute name. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.
`typep` Pointer to location for returned attribute type.
`lenp` Pointer to location for returned attribute number.

4.4.3. Define an integer attribute: `vlistDefAttInt`

The function `vlistDefAttInt` defines an integer attribute.

Usage

```
int vlistDefAttInt(int vlistID, int varID, const char *name, int type, int len,
                  const int *ip);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or `CDI_GLOBAL` for a global attribute.
name Attribute name.
type External data type (`DATATYPE_INT16` or `DATATYPE_INT32`).
len Number of values provided for the attribute.
ip Pointer to one or more integer values.

4.4.4. Get the value(s) of an integer attribute: vlistInqAttInt

The function `vlistInqAttInt` gets the values(s) of an integer attribute.

Usage

```
int vlistInqAttInt(int vlistID, int varID, const char *name, int mlen, int *ip);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or `CDI_GLOBAL` for a global attribute.
name Attribute name.
mlen Number of allocated values provided for the attribute.
ip Pointer location for returned integer attribute value(s).

4.4.5. Define a floating point attribute: vlistDefAttFlt

The function `vlistDefAttFlt` defines a floating point attribute.

Usage

```
int vlistDefAttFlt(int vlistID, int varID, const char *name, int type, int len,
                  const double *dp);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or `CDI_GLOBAL` for a global attribute.
name Attribute name.
type External data type (`DATATYPE_FLT32` or `DATATYPE_FLT64`).
len Number of values provided for the attribute.
dp Pointer to one or more floating point values.

4.4.6. Get the value(s) of a floating point attribute: vlistInqAttFlt

The function `vlistInqAttFlt` gets the values(s) of a floating point attribute.

Usage

```
int vlistInqAttFlt(int vlistID, int varID, const char *name, int mlen, int *dp);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or `CDI_GLOBAL` for a global attribute.
name Attribute name.
mlen Number of allocated values provided for the attribute.
dp Pointer location for returned floating point attribute value(s).

4.4.7. Define a text attribute: `vlistDefAttTxt`

The function `vlistDefAttTxt` defines a text attribute.

Usage

```
int vlistDefAttTxt(int vlistID, int varID, const char *name, int len, const char *tp);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or `CDI_GLOBAL` for a global attribute.
name Attribute name.
len Number of values provided for the attribute.
tp Pointer to one or more character values.

4.4.8. Get the value(s) of a text attribute: `vlistInqAttTxt`

The function `vlistInqAttTxt` gets the values(s) of a text attribute.

Usage

```
int vlistInqAttTxt(int vlistID, int varID, const char *name, int mlen, int *tp);
```

vlistID Variable list ID, from a previous call to [vlistCreate](#).
varID Variable identifier, or `CDI_GLOBAL` for a global attribute.
name Attribute name.
mlen Number of allocated values provided for the attribute.
tp Pointer location for returned text attribute value(s).

4.5. Grid functions

This module contains functions to define a new horizontal Grid and to get information from an existing Grid. A Grid object is necessary to define a variable. The following different Grid types are available:

GRID_GENERIC	Generic user defined grid
GRID_LONLAT	Regular longitude/latitude grid
GRID_GAUSSIAN	Regular Gaussian lon/lat grid
GRID_SPECTRAL	Spherical harmonic coefficients
GRID_GME	Icosahedral-hexagonal GME grid
GRID_CURVILINEAR	Curvilinear grid
GRID_UNSTRUCTURED	Unstructured grid
GRID_LCC	Lambert conformal conic grid
GRID_REFERENCE	Grid reference number

4.5.1. Create a horizontal Grid: `gridCreate`

The function `gridCreate` creates a horizontal Grid.

Usage

```
int gridCreate(int gridtype, int size);
```

gridtype The type of the grid, one of the set of predefined **CDI** grid types. The valid **CDI** grid types are `GRID_GENERIC`, `GRID_GAUSSIAN`, `GRID_LONLAT`, `GRID_LCC`, `GRID_SPECTRAL`, `GRID_GME`, `GRID_CURVILINEAR`, `GRID_UNSTRUCTURED` and `GRID_REFERENCE`.

size Number of gridpoints.

Result

`gridCreate` returns an identifier to the Grid.

Example

Here is an example using `gridCreate` to create a regular lon/lat Grid:

```
#include "cdi.h"
...
#define nlon 12
#define nlat 6
...
double lons[nlon] = {0, 30, 60, 90, 120, 150, 180, 210, 240, 270, 300, 330};
double lats[nlat] = {-75, -45, -15, 15, 45, 75};
int gridID;
...
gridID = gridCreate(GRID_LONLAT, nlon*nlat);
gridDefXsize(gridID, nlon);
gridDefYsize(gridID, nlat);
gridDefXvals(gridID, lons);
gridDefYvals(gridID, lats);
...
```

4.5.2. Destroy a horizontal Grid: `gridDestroy`

Usage

```
void gridDestroy(int gridID);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

4.5.3. Duplicate a horizontal Grid: `gridDuplicate`

The function `gridDuplicate` duplicates a horizontal Grid.

Usage

```
int gridDuplicate(int gridID);
```

`gridID` Grid ID, from a previous call to [gridCreate](#), [gridDuplicate](#) or [vlistInqVarGrid](#).

Result

`gridDuplicate` returns an identifier to the duplicated Grid.

4.5.4. Get the type of a Grid: `gridInqType`

The function `gridInqType` returns the type of a Grid.

Usage

```
int gridInqType(int gridID);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

Result

`gridInqType` returns the type of the grid, one of the set of predefined **CDI** grid types. The valid **CDI** grid types are `GRID_GENERIC`, `GRID_GAUSSIAN`, `GRID_LONLAT`, `GRID_LCC`, `GRID_SPECTRAL`, `GRID_GME`, `GRID_CURVILINEAR`, `GRID_UNSTRUCTURED` and `GRID_REFERENCE`.

4.5.5. Get the size of a Grid: `gridInqSize`

The function `gridInqSize` returns the size of a Grid.

Usage

```
int gridInqSize(int gridID);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

Result

`gridInqSize` returns the number of grid points of a Grid.

4.5.6. Define the number of values of a X-axis: `gridDefXsize`

The function `gridDefXsize` defines the number of values of a X-axis.

Usage

```
void gridDefXsize(int gridID, int xsize);
```

gridID Grid ID, from a previous call to [gridCreate](#).
xsize Number of values of a X-axis.

4.5.7. Get the number of values of a X-axis: gridInqXsize

The function `gridInqXsize` returns the number of values of a X-axis.

Usage

```
int gridInqXsize(int gridID);
```

gridID Grid ID, from a previous call to [gridCreate](#).

Result

`gridInqXsize` returns the number of values of a X-axis.

4.5.8. Define the number of values of a Y-axis: gridDefYsize

The function `gridDefYsize` defines the number of values of a Y-axis.

Usage

```
void gridDefYsize(int gridID, int ysize);
```

gridID Grid ID, from a previous call to [gridCreate](#).
ysize Number of values of a Y-axis.

4.5.9. Get the number of values of a Y-axis: gridInqYsize

The function `gridInqYsize` returns the number of values of a Y-axis.

Usage

```
int gridInqYsize(int gridID);
```

gridID Grid ID, from a previous call to [gridCreate](#).

Result

`gridInqYsize` returns the number of values of a Y-axis.

4.5.10. Define the number of parallels between a pole and the equator: gridDefNP

The function `gridDefNP` defines the number of parallels between a pole and the equator of a Gaussian grid.

Usage

```
void gridDefNP(int gridID, int np);
```

gridID Grid ID, from a previous call to [gridCreate](#).
np Number of parallels between a pole and the equator.

4.5.11. Get the number of parallels between a pole and the equator: `gridInqNP`

The function `gridInqNP` returns the number of parallels between a pole and the equator of a Gaussian grid.

Usage

```
int gridInqNP(int gridID);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

Result

`gridInqNP` returns the number of parallels between a pole and the equator.

4.5.12. Define the values of a X-axis: `gridDefXvals`

The function `gridDefXvals` defines all values of the X-axis.

Usage

```
void gridDefXvals(int gridID, const double *xvals);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`xvals` X-values of the grid.

4.5.13. Get all values of a X-axis: `gridInqXvals`

The function `gridInqXvals` returns all values of the X-axis.

Usage

```
int gridInqXvals(int gridID, double *xvals);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`xvals` Pointer to the location into which the X-values are read. The caller must allocate space for the returned values.

Result

Upon successful completion `gridInqXvals` returns the number of values and the values are stored in `xvals`. Otherwise, 0 is returned and `xvals` is empty.

4.5.14. Define the values of a Y-axis: `gridDefYvals`

The function `gridDefYvals` defines all values of the Y-axis.

Usage

```
void gridDefYvals(int gridID, const double *yvals);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`yvals` Y-values of the grid.

4.5.15. Get all values of a Y-axis: gridInqYvals

The function `gridInqYvals` returns all values of the Y-axis.

Usage

```
int gridInqYvals(int gridID, double *yvals);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`yvals` Pointer to the location into which the Y-values are read. The caller must allocate space for the returned values.

Result

Upon successful completion `gridInqYvals` returns the number of values and the values are stored in `yvals`. Otherwise, 0 is returned and `yvals` is empty.

4.5.16. Define the bounds of a X-axis: gridDefXbounds

The function `gridDefXbounds` defines all bounds of the X-axis.

Usage

```
void gridDefXbounds(int gridID, const double *xbounds);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`xbounds` X-bounds of the grid.

4.5.17. Get the bounds of a X-axis: gridInqXbounds

The function `gridInqXbounds` returns the bounds of the X-axis.

Usage

```
int gridInqXbounds(int gridID, double *xbounds);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`xbounds` Pointer to the location into which the X-bounds are read. The caller must allocate space for the returned values.

Result

Upon successful completion `gridInqXbounds` returns the number of bounds and the bounds are stored in `xbounds`. Otherwise, 0 is returned and `xbounds` is empty.

4.5.18. Define the bounds of a Y-axis: gridDefYbounds

The function `gridDefYbounds` defines all bounds of the Y-axis.

Usage

```
void gridDefYbounds(int gridID, const double *ybounds);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`ybounds` Y-bounds of the grid.

4.5.19. Get the bounds of a Y-axis: `gridInqYbounds`

The function `gridInqYbounds` returns the bounds of the Y-axis.

Usage

```
int gridInqYbounds(int gridID, double *ybounds);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`ybounds` Pointer to the location into which the Y-bounds are read. The caller must allocate space for the returned values.

Result

Upon successful completion `gridInqYbounds` returns the number of bounds and the bounds are stored in `ybounds`. Otherwise, 0 is returned and `ybounds` is empty.

4.5.20. Define the name of a X-axis: `gridDefXname`

The function `gridDefXname` defines the name of a X-axis.

Usage

```
void gridDefXname(int gridID, const char *name);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`name` Name of the X-axis.

4.5.21. Get the name of a X-axis: `gridInqXname`

The function `gridInqXname` returns the name of a X-axis.

Usage

```
void gridInqXname(int gridID, char *name);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`name` Name of the X-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqXname` returns the name of the X-axis to the parameter `name`.

4.5.22. Define the longname of a X-axis: `gridDefXlongname`

The function `gridDefXlongname` defines the longname of a X-axis.

Usage

```
void gridDefXlongname(int gridID, const char *longname);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`longname` Longname of the X-axis.

4.5.23. Get the longname of a X-axis: `gridInqXlongname`

The function `gridInqXlongname` returns the longname of a X-axis.

Usage

```
void gridInqXlongname(int gridID, char *longname);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`longname` Longname of the X-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqXlongname` returns the longname of the X-axis to the parameter `longname`.

4.5.24. Define the units of a X-axis: `gridDefXunits`

The function `gridDefXunits` defines the units of a X-axis.

Usage

```
void gridDefXunits(int gridID, const char *units);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`units` Units of the X-axis.

4.5.25. Get the units of a X-axis: `gridInqXunits`

The function `gridInqXunits` returns the units of a X-axis.

Usage

```
void gridInqXunits(int gridID, char *units);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`units` Units of the X-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqXunits` returns the units of the X-axis to the parameter `units`.

4.5.26. Define the name of a Y-axis: `gridDefYname`

The function `gridDefYname` defines the name of a Y-axis.

Usage

```
void gridDefYname(int gridID, const char *name);
```

`gridID` Grid ID, from a previous call to `gridCreate`.

`name` Name of the Y-axis.

4.5.27. Get the name of a Y-axis: gridInqYname

The function `gridInqYname` returns the name of a Y-axis.

Usage

```
void gridInqYname(int gridID, char *name);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`name` Name of the Y-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqYname` returns the name of the Y-axis to the parameter `name`.

4.5.28. Define the longname of a Y-axis: gridDefYlongname

The function `gridDefYlongname` defines the longname of a Y-axis.

Usage

```
void gridDefYlongname(int gridID, const char *longname);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`longname` Longname of the Y-axis.

4.5.29. Get the longname of a Y-axis: gridInqYlongname

The function `gridInqYlongname` returns the longname of a Y-axis.

Usage

```
void gridInqXlongname(int gridID, char *longname);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`longname` Longname of the Y-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqYlongname` returns the longname of the Y-axis to the parameter `longname`.

4.5.30. Define the units of a Y-axis: gridDefYunits

The function `gridDefYunits` defines the units of a Y-axis.

Usage

```
void gridDefYunits(int gridID, const char *units);
```

`gridID` Grid ID, from a previous call to [gridCreate](#).

`units` Units of the Y-axis.

4.5.31. Get the units of a Y-axis: gridInqYunits

The function `gridInqYunits` returns the units of a Y-axis.

Usage

```
void gridInqYunits(int gridID, char *units);
```

gridID Grid ID, from a previous call to [gridCreate](#).

units Units of the Y-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`gridInqYunits` returns the units of the Y-axis to the parameter `units`.

4.6. Z-axis functions

This section contains functions to define a new vertical Z-axis and to get information from an existing Z-axis. A Z-axis object is necessary to define a variable. The following different Z-axis types are available:

ZAXIS_GENERIC	Generic user defined level
ZAXIS_SURFACE	Surface level
ZAXIS_MEANSEA	Mean sea level
ZAXIS_TOA	Norminal top of atmosphere
ZAXIS_ATMOSPHERE	Entire atmosphere
ZAXIS_SEA_BOTTOM	Sea bottom
ZAXIS_ISENTROPIC	Isentropic (theta) level
ZAXIS_HYBRID	Hybrid level
ZAXIS_SIGMA	Sigma level
ZAXIS_PRESSURE	Isobaric pressure level in Pascal
ZAXIS_HEIGHT	Height above ground in meters
ZAXIS_ALTITUDE	Altitude above mean sea level in meters
ZAXIS_CLOUD_BASE	Cloud base level
ZAXIS_CLOUD_TOP	Level of cloud tops
ZAXIS_ISOTHERM_ZERO	Level of 0° C isotherm
ZAXIS_DEPTH_BELOW_SEA	Depth below sea level in meters
ZAXIS_DEPTH_BELOW_LAND	Depth below land surface in centimeters

4.6.1. Create a vertical Z-axis: `zaxisCreate`

The function `zaxisCreate` creates a vertical Z-axis.

Usage

```
int zaxisCreate(int zaxistype, int size);
```

zaxistype The type of the Z-axis, one of the set of predefined **CDI** Z-axis types. The valid **CDI** Z-axis types are `ZAXIS_GENERIC`, `ZAXIS_SURFACE`, `ZAXIS_HYBRID`, `ZAXIS_SIGMA`, `ZAXIS_PRESSURE`, `ZAXIS_HEIGHT`, `ZAXIS_ISENTROPIC`, `ZAXIS_ALTITUDE`, `ZAXIS_MEANSEA`, `ZAXIS_TOA`, `ZAXIS_SEA_BOTTOM`, `ZAXIS_ATMOSPHERE`, `ZAXIS_CLOUD_BASE`, `ZAXIS_CLOUD_TOP`, `ZAXIS_ISOTHERM_ZERO`, `ZAXIS_DEPTH_BELOW_SEA` and `ZAXIS_DEPTH_BELOW_LAND`.

size Number of levels.

Result

`zaxisCreate` returns an identifier to the Z-axis.

Example

Here is an example using `zaxisCreate` to create a pressure level Z-axis:

```
#include "cdi.h"
```



```
...
#define nlev 5
...
double levs[nlev] = {101300, 92500, 85000, 50000, 20000};
int zaxisID;
...
zaxisID = zaxisCreate(ZAXIS_PRESSURE, nlev);
zaxisDefLevels(zaxisID, levs);
...
```

4.6.2. Destroy a vertical Z-axis: `zaxisDestroy`

Usage

```
void zaxisDestroy(int zaxisID);
```

`zaxisID` Z-axis ID, from a previous call to [zaxisCreate](#).

4.6.3. Get the type of a Z-axis: `zaxisInqType`

The function `zaxisInqType` returns the type of a Z-axis.

Usage

```
int zaxisInqType(int zaxisID);
```

`zaxisID` Z-axis ID, from a previous call to [zaxisCreate](#).

Result

`zaxisInqType` returns the type of the Z-axis, one of the set of predefined **CDI** Z-axis types. The valid **CDI** Z-axis types are `ZAXIS_GENERIC`, `ZAXIS_SURFACE`, `ZAXIS_HYBRID`, `ZAXIS_SIGMA`, `ZAXIS_PRESSURE`, `ZAXIS_HEIGHT`, `ZAXIS_ISENTROPIC`, `ZAXIS_ALTITUDE`, `ZAXIS_MEANSEA`, `ZAXIS_TOA`, `ZAXIS_SEA_BOTTOM`, `ZAXIS_ATMOSPHERE`, `ZAXIS_CLOUD_BASE`, `ZAXIS_CLOUD_TOP`, `ZAXIS_ISOTHERM_ZERO`, `ZAXIS_DEPTH_BELOW_SEA` and `ZAXIS_DEPTH_BELOW_LAND`.

4.6.4. Get the size of a Z-axis: `zaxisInqSize`

The function `zaxisInqSize` returns the size of a Z-axis.

Usage

```
int zaxisInqSize(int zaxisID);
```

`zaxisID` Z-axis ID, from a previous call to [zaxisCreate](#)

Result

`zaxisInqSize` returns the number of levels of a Z-axis.

4.6.5. Define the levels of a Z-axis: `zaxisDefLevels`

The function `zaxisDefLevels` defines the levels of a Z-axis.

Usage

```
void zaxisDefLevels(int zaxisID, const double *levels);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

levels All levels of the Z-axis.

4.6.6. Get all levels of a Z-axis: zaxisInqLevels

The function `zaxisInqLevels` returns all levels of a Z-axis.

Usage

```
void zaxisInqLevels(int zaxisID, double *levels);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

levels Pointer to the location into which the levels are read. The caller must allocate space for the returned values.

Result

`zaxisInqLevels` saves all levels to the parameter `levels`.

4.6.7. Get one level of a Z-axis: zaxisInqLevel

The function `zaxisInqLevel` returns one level of a Z-axis.

Usage

```
double zaxisInqLevel(int zaxisID, int levelID);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

levelID Level index (range: 0 to `nlevel-1`).

Result

`zaxisInqLevel` returns the level of a Z-axis.

4.6.8. Define the name of a Z-axis: zaxisDefName

The function `zaxisDefName` defines the name of a Z-axis.

Usage

```
void zaxisDefName(int zaxisID, const char *name);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

name Name of the Z-axis.

4.6.9. Get the name of a Z-axis: zaxisInqName

The function `zaxisInqName` returns the name of a Z-axis.

Usage

```
void zaxisInqName(int zaxisID, char *name);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

name Name of the Z-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`zaxisInqName` returns the name of the Z-axis to the parameter `name`.

4.6.10. Define the longname of a Z-axis: `zaxisDefLongname`

The function `zaxisDefLongname` defines the longname of a Z-axis.

Usage

```
void zaxisDefLongname(int zaxisID, const char *longname);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

longname Longname of the Z-axis.

4.6.11. Get the longname of a Z-axis: `zaxisInqLongname`

The function `zaxisInqLongname` returns the longname of a Z-axis.

Usage

```
void zaxisInqLongname(int zaxisID, char *longname);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

longname Longname of the Z-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`zaxisInqLongname` returns the longname of the Z-axis to the parameter `longname`.

4.6.12. Define the units of a Z-axis: `zaxisDefUnits`

The function `zaxisDefUnits` defines the units of a Z-axis.

Usage

```
void zaxisDefUnits(int zaxisID, const char *units);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#).

units Units of the Z-axis.

4.6.13. Get the units of a Z-axis: `zaxisInqUnits`

The function `zaxisInqUnits` returns the units of a Z-axis.

Usage

```
void zaxisInqUnits(int zaxisID, char *units);
```

zaxisID Z-axis ID, from a previous call to [zaxisCreate](#)

units Units of the Z-axis. The caller must allocate space for the returned string. The maximum possible length, in characters, of the string is given by the predefined constant `CDI_MAX_NAME`.

Result

`zaxisInqUnits` returns the units of the Z-axis to the parameter `units`.

4.7. T-axis functions

This section contains functions to define a new Time axis and to get information from an existing T-axis. A T-axis object is necessary to define the time axis of a dataset and must be assigned to a variable list using `vlistDefTaxis`. The following different Time axis types are available:

<code>TAXIS_ABSOLUTE</code>	Absolute time axis
<code>TAXIS_RELATIVE</code>	Relative time axis

An absolute time axis has the current time to each time step. It can be used without knowledge of the calendar.

A relative time is the time relative to a fixed reference time. The current time results from the reference time and the elapsed interval. The result depends on the used calendar. CDI supports the following calendar types:

<code>CALENDAR_STANDARD</code>	Mixed Gregorian/Julian calendar.
<code>CALENDAR_PROLEPTIC</code>	Proleptic Gregorian calendar. This is the default.
<code>CALENDAR_360DAYS</code>	All years are 360 days divided into 30 day months.
<code>CALENDAR_365DAYS</code>	Gregorian calendar without leap years, i.e., all years are 365 days long.
<code>CALENDAR_366DAYS</code>	Gregorian calendar with every year being a leap year, i.e., all years are 366 days long.

4.7.1. Create a Time axis: `taxisCreate`

The function `taxisCreate` creates a Time axis.

Usage

```
int taxisCreate(int taxistype);
```

taxistype The type of the Time axis, one of the set of predefined **CDI** time axis types.
The valid **CDI** time axis types are `TAXIS_ABSOLUTE` and `TAXIS_RELATIVE`.

Result

`taxisCreate` returns an identifier to the Time axis.

Example

Here is an example using `taxisCreate` to create a relative T-axis with a standard calendar.

```
#include "cdi.h"
...
int taxisID;
...
taxisID = taxisCreate(TAXIS_RELATIVE);
taxisDefCalendar(taxisID, CALENDAR_STANDARD);
taxisDefRdate(taxisID, 19850101);
taxisDefRtime(taxisID, 120000);
...
```

4.7.2. Destroy a Time axis: `taxisDestroy`

Usage

```
void taxisDestroy(int taxisID);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

4.7.3. Define the reference date: `taxisDefRdate`

The function `taxisDefVdate` defines the reference date of a Time axis.

Usage

```
void taxisDefRdate(int taxisID, int rdate);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

`rdate` Reference date (YYYYMMDD)

4.7.4. Get the reference date: `taxisInqRdate`

The function `taxisInqRdate` returns the reference date of a Time axis.

Usage

```
int taxisInqRdate(int taxisID);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

Result

`taxisInqVdate` returns the reference date.

4.7.5. Define the reference time: `taxisDefRtime`

The function `taxisDefVdate` defines the reference time of a Time axis.

Usage

```
void taxisDefRtime(int taxisID, int rtime);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

`rtime` Reference time (hhmmss)

4.7.6. Get the reference time: `taxisInqRtime`

The function `taxisInqRtime` returns the reference time of a Time axis.

Usage

```
int taxisInqRtime(int taxisID);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

Result

`taxisInqVtime` returns the reference time.

4.7.7. Define the verification date: `taxisDefVdate`

The function `taxisDefVdate` defines the verification date of a Time axis.

Usage

```
void taxisDefVdate(int taxisID, int vdate);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`
`vdate` Verification date (YYYYMMDD)

4.7.8. Get the verification date: `taxisInqVdate`

The function `taxisInqVdate` returns the verification date of a Time axis.

Usage

```
int taxisInqVdate(int taxisID);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

Result

`taxisInqVdate` returns the verification date.

4.7.9. Define the verification time: `taxisDefVtime`

The function `taxisDefVtime` defines the verification time of a Time axis.

Usage

```
void taxisDefVtime(int taxisID, int vtime);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`
`vtime` Verification time (hhmmss)

4.7.10. Get the verification time: `taxisInqVtime`

The function `taxisInqVtime` returns the verification time of a Time axis.

Usage

```
int taxisInqVtime(int taxisID);
```

`taxisID` Time axis ID, from a previous call to `taxisCreate`

Result

`taxisInqVtime` returns the verification time.

4.7.11. Define the calendar: `taxisDefCalendar`

The function `taxisDefCalendar` defines the calendar of a Time axis.

Usage

```
void taxisDefCalendar(int taxisID, int calendar);
```

taxisID Time axis ID, from a previous call to [taxisCreate](#)

calendar The type of the calendar, one of the set of predefined **CDI** calendar types. The valid **CDI** calendar types are `CALENDAR_STANDARD`, `CALENDAR_PROLEPTIC`, `CALENDAR_360DAYS`, `CALENDAR_365DAYS` and `CALENDAR_366DAYS`.

4.7.12. Get the calendar: taxisInqCalendar

The function `taxisInqCalendar` returns the calendar of a Time axis.

Usage

```
int taxisInqCalendar(int taxisID);
```

taxisID Time axis ID, from a previous call to [taxisCreate](#)

Result

`taxisInqCalendar` returns the type of the calendar, one of the set of predefined **CDI** calendar types. The valid **CDI** calendar types are `CALENDAR_STANDARD`, `CALENDAR_PROLEPTIC`, `CALENDAR_360DAYS`, `CALENDAR_365DAYS` and `CALENDAR_366DAYS`.

Bibliography

[ECHAM]

The atmospheric general circulation model [ECHAM5](#), from the [Max Planck Institute for Meteorologie](#)

[GRIB]

[GRIB version 1](#), from the World Meteorological Organisation ([WMO](#))

[GRIBAPI]

[GRIB API decoding/encoding](#), from the European Centre for Medium-Range Weather Forecasts ([ECMWF](#))

[HDF5]

[HDF version 5](#), from the HDF Group

[NetCDF]

[NetCDF Software Package](#), from the [UNIDATA](#) Program Center of the University Corporation for Atmospheric Research

[MPIOM]

The ocean model MPIOM, from the [Max Planck Institute for Meteorologie](#)

[REMO]

The regional climate model REMO, from the [Max Planck Institute for Meteorologie](#)

A. Quick Reference

This appendix provide a brief listing of the C language bindings of the CDI library routines:

`gridCreate`

```
int gridCreate(int gridtype, int size);
```

Create a horizontal Grid

`gridDefNP`

```
void gridDefNP(int gridID, int np);
```

Define the number of parallels between a pole and the equator

`gridDefXbounds`

```
void gridDefXbounds(int gridID, const double *xbounds);
```

Define the bounds of a X-axis

`gridDefXlongname`

```
void gridDefXlongname(int gridID, const char *longname);
```

Define the longname of a X-axis

`gridDefXname`

```
void gridDefXname(int gridID, const char *name);
```

Define the name of a X-axis

`gridDefXsize`

```
void gridDefXsize(int gridID, int xsize);
```

Define the number of values of a X-axis

`gridDefXunits`

```
void gridDefXunits(int gridID, const char *units);
```

Define the units of a X-axis

[gridDefXvals](#)

```
void gridDefXvals(int gridID, const double *xvals);
```

Define the values of a X-axis

[gridDefYbounds](#)

```
void gridDefYbounds(int gridID, const double *ybounds);
```

Define the bounds of a Y-axis

[gridDefYlongname](#)

```
void gridDefYlongname(int gridID, const char *longname);
```

Define the longname of a Y-axis

[gridDefYname](#)

```
void gridDefYname(int gridID, const char *name);
```

Define the name of a Y-axis

[gridDefYsize](#)

```
void gridDefYsize(int gridID, int ysize);
```

Define the number of values of a Y-axis

[gridDefYunits](#)

```
void gridDefYunits(int gridID, const char *units);
```

Define the units of a Y-axis

[gridDefYvals](#)

```
void gridDefYvals(int gridID, const double *yvals);
```

Define the values of a Y-axis

[gridDestroy](#)

```
void gridDestroy(int gridID);
```

Destroy a horizontal Grid

gridDuplicate

```
int gridDuplicate(int gridID);
```

Duplicate a horizontal Grid

gridInqNP

```
int gridInqNP(int gridID);
```

Get the number of parallels between a pole and the equator

gridInqSize

```
int gridInqSize(int gridID);
```

Get the size of a Grid

gridInqType

```
int gridInqType(int gridID);
```

Get the type of a Grid

gridInqXbounds

```
int gridInqXbounds(int gridID, double *xbounds);
```

Get the bounds of a X-axis

gridInqXlongname

```
void gridInqXlongname(int gridID, char *longname);
```

Get the longname of a X-axis

gridInqXname

```
void gridInqXname(int gridID, char *name);
```

Get the name of a X-axis

gridInqXsize

```
int gridInqXsize(int gridID);
```

Get the number of values of a X-axis

gridInqXunits

```
void gridInqXunits(int gridID, char *units);
```

Get the units of a X-axis

gridInqXvals

```
int gridInqXvals(int gridID, double *xvals);
```

Get all values of a X-axis

gridInqYbounds

```
int gridInqYbounds(int gridID, double *ybounds);
```

Get the bounds of a Y-axis

gridInqYlongname

```
void gridInqYlongname(int gridID, char *longname);
```

Get the longname of a Y-axis

gridInqYname

```
void gridInqYname(int gridID, char *name);
```

Get the name of a Y-axis

gridInqYsize

```
int gridInqYsize(int gridID);
```

Get the number of values of a Y-axis

gridInqYunits

```
void gridInqYunits(int gridID, char *units);
```

Get the units of a Y-axis

gridInqYvals

```
int gridInqYvals(int gridID, double *yvals);
```

Get all values of a Y-axis

streamClose

```
void streamClose(int streamID);
```

Close an open dataset

streamDefByteorder

```
void streamDefByteorder(int streamID, int byteorder);
```

Define the byte order

streamDefTimestep

```
int streamDefTimestep(int streamID, int tsID);
```

Define time step

streamDefVlist

```
void streamDefVlist(int streamID, int vlistID);
```

Define the variable list

streamInqByteorder

```
int streamInqByteorder(int streamID);
```

Get the byte order

streamInqFiletype

```
int streamInqFiletype(int streamID);
```

Get the filetype

streamInqTimestep

```
int streamInqTimestep(int streamID, int tsID);
```

Get time step

streamInqVlist

```
int streamInqVlist(int streamID);
```

Get the variable list

streamOpenRead

```
int streamOpenRead(const char *path);
```

Open a dataset for reading

streamOpenWrite

```
int streamOpenWrite(const char *path, int filetype);
```

Create a new dataset

streamReadVar

```
void streamReadVar(int streamID, int varID, double *data, int *nmiss);
```

Read a variable

streamReadVarSlice

```
void streamReadVarSlice(int streamID, int varID, int levelID, double *data,  
                        int *nmiss);
```

Read a horizontal slice of a variable

streamWriteVar

```
void streamWriteVar(int streamID, int varID, const double *data, int nmiss);
```

Write a variable

streamWriteVarF

```
void streamWriteVarF(int streamID, int varID, const float *data, int nmiss);
```

Write a variable

streamWriteVarSlice

```
void streamWriteVarSlice(int streamID, int varID, int levelID, const double *data,  
                        int nmiss);
```

Write a horizontal slice of a variable

streamWriteVarSliceF

```
void streamWriteVarSliceF(int streamID, int varID, int levelID, const float *data,  
                        int nmiss);
```

Write a horizontal slice of a variable

`taxisCreate`

```
int taxisCreate(int taxistype);
```

Create a Time axis

`taxisDefCalendar`

```
void taxisDefCalendar(int taxisID, int calendar);
```

Define the calendar

`taxisDefRdate`

```
void taxisDefRdate(int taxisID, int rdate);
```

Define the reference date

`taxisDefRtime`

```
void taxisDefRtime(int taxisID, int rtime);
```

Define the reference time

`taxisDefVdate`

```
void taxisDefVdate(int taxisID, int vdate);
```

Define the verification date

`taxisDefVtime`

```
void taxisDefVtime(int taxisID, int vtime);
```

Define the verification time

`taxisDestroy`

```
void taxisDestroy(int taxisID);
```

Destroy a Time axis

`taxisInqCalendar`

```
int taxisInqCalendar(int taxisID);
```

Get the calendar

`taxisInqRdate`

```
int taxisInqRdate(int taxisID);
```

Get the reference date

`taxisInqRtime`

```
int taxisInqRtime(int taxisID);
```

Get the reference time

`taxisInqVdate`

```
int taxisInqVdate(int taxisID);
```

Get the verification date

`taxisInqVtime`

```
int taxisInqVtime(int taxisID);
```

Get the verification time

`vlistCat`

```
void vlistCat(int vlistID2, int vlistID1);
```

Concatenate two variable lists

`vlistCopy`

```
void vlistCopy(int vlistID2, int vlistID1);
```

Copy a variable list

`vlistCopyFlag`

```
void vlistCopyFlag(int vlistID2, int vlistID1);
```

Copy some entries of a variable list

`vlistCreate`

```
int vlistCreate(void);
```

Create a variable list

`vlistDefAttFlt`

```
int vlistDefAttFlt(int vlistID, int varID, const char *name, int type, int len,
                  const double *dp);
```

Define a floating point attribute

`vlistDefAttInt`

```
int vlistDefAttInt(int vlistID, int varID, const char *name, int type, int len,
                  const int *ip);
```

Define an integer attribute

`vlistDefAttTxt`

```
int vlistDefAttTxt(int vlistID, int varID, const char *name, int len, const char *tp);
```

Define a text attribute

`vlistDefTaxis`

```
void vlistDefTaxis(int vlistID, int taxisID);
```

Define the time axis

`vlistDefVar`

```
int vlistDefVar(int vlistID, int gridID, int zaxisID, int tsteptype);
```

Define a Variable

`vlistDefVarCode`

```
void vlistDefVarCode(int vlistID, int varID, int code);
```

Define the code number of a Variable

`vlistDefVarDatatype`

```
void vlistDefVarDatatype(int vlistID, int varID, int datatype);
```

Define the data type of a Variable

`vlistDefVarLongname`

```
void vlistDefVarLongname(int vlistID, int varID, const char *longname);
```

Define the long name of a Variable

`vlistDefVarMissval`

```
void vlistDefVarMissval(int vlistID, int varID, double missval);
```

Define the missing value of a Variable

`vlistDefVarName`

```
void vlistDefVarName(int vlistID, int varID, const char *name);
```

Define the name of a Variable

`vlistDefVarStdname`

```
void vlistDefVarStdname(int vlistID, int varID, const char *stdname);
```

Define the standard name of a Variable

`vlistDefVarUnits`

```
void vlistDefVarUnits(int vlistID, int varID, const char *units);
```

Define the units of a Variable

`vlistDestroy`

```
void vlistDestroy(int vlistID);
```

Destroy a variable list

`vlistDuplicate`

```
int vlistDuplicate(int vlistID);
```

Duplicate a variable list

`vlistInqAtt`

```
int vlistInqAtt(int vlistID, int varID, int attnum, char *name, int *typep, int *lenp);
```

Get information about an attribute

`vlistInqAttFlt`

```
int vlistInqAttFlt(int vlistID, int varID, const char *name, int mlen, int *dp);
```

Get the value(s) of a floating point attribute

`vlistInqAttInt`

```
int vlistInqAttInt(int vlistID, int varID, const char *name, int mlen, int *ip);
```

Get the value(s) of an integer attribute

`vlistInqAttTxt`

```
int vlistInqAttTxt(int vlistID, int varID, const char *name, int mlen, int *tp);
```

Get the value(s) of a text attribute

`vlistInqNatts`

```
int vlistInqNatts(int vlistID, int varID, int *nattsp);
```

Get number of variable attributes

`vlistInqTaxis`

```
int vlistInqTaxis(int vlistID);
```

Get the time axis

`vlistInqVarCode`

```
int vlistInqVarCode(int vlistID, int varID);
```

Get the Code number of a Variable

`vlistInqVarDatatype`

```
int vlistInqVarDatatype(int vlistID, int varID);
```

Get the data type of a Variable

`vlistInqVarGrid`

```
int vlistInqVarGrid(int vlistID, int varID);
```

Get the Grid ID of a Variable

`vlistInqVarLongname`

```
void vlistInqVarLongname(int vlistID, int varID, char *longname);
```

Get the longname of a Variable

`vlistInqVarMissval`

```
double vlistInqVarMissval(int vlistID, int varID);
```

Get the missing value of a Variable

`vlistInqVarName`

```
void vlistInqVarName(int vlistID, int varID, char *name);
```

Get the name of a Variable

`vlistInqVarStdname`

```
void vlistInqVarStdname(int vlistID, int varID, char *stdname);
```

Get the standard name of a Variable

`vlistInqVarUnits`

```
void vlistInqVarUnits(int vlistID, int varID, char *units);
```

Get the units of a Variable

`vlistInqVarZaxis`

```
int vlistInqVarZaxis(int vlistID, int varID);
```

Get the Zaxis ID of a Variable

`vlistNgrids`

```
int vlistNgrids(int vlistID);
```

Number of grids in a variable list

`vlistNvars`

```
int vlistNvars(int vlistID);
```

Number of variables in a variable list

`vlistNzaxis`

```
int vlistNzaxis(int vlistID);
```

Number of zaxis in a variable list

zaxisCreate

```
int zaxisCreate(int zaxistype, int size);
```

Create a vertical Z-axis

zaxisDefLevels

```
void zaxisDefLevels(int zaxisID, const double *levels);
```

Define the levels of a Z-axis

zaxisDefLongname

```
void zaxisDefLongname(int zaxisID, const char *longname);
```

Define the longname of a Z-axis

zaxisDefName

```
void zaxisDefName(int zaxisID, const char *name);
```

Define the name of a Z-axis

zaxisDefUnits

```
void zaxisDefUnits(int zaxisID, const char *units);
```

Define the units of a Z-axis

zaxisDestroy

```
void zaxisDestroy(int zaxisID);
```

Destroy a vertical Z-axis

zaxisInqLevel

```
double zaxisInqLevel(int zaxisID, int levelID);
```

Get one level of a Z-axis

zaxisInqLevels

```
void zaxisInqLevels(int zaxisID, double *levels);
```

Get all levels of a Z-axis

zaxisInqLongname

```
void zaxisInqLongname(int zaxisID, char *longname);
```

Get the longname of a Z-axis

zaxisInqName

```
void zaxisInqName(int zaxisID, char *name);
```

Get the name of a Z-axis

zaxisInqSize

```
int zaxisInqSize(int zaxisID);
```

Get the size of a Z-axis

zaxisInqType

```
int zaxisInqType(int zaxisID);
```

Get the type of a Z-axis

zaxisInqUnits

```
void zaxisInqUnits(int zaxisID, char *units);
```

Get the units of a Z-axis

B. Examples

This appendix contains complete examples to write, read and copy a dataset with the **CDI** library.

B.1. Write a dataset

Here is an example using **CDI** to write a netCDF dataset with 2 variables on 3 time steps. The first variable is a 2D field on surface level and the second variable is a 3D field on 5 pressure levels. Both variables are on the same lon/lat grid.

```
#include <stdio.h>
#include "cdi.h"

#define nlon 12 // Number of longitudes
5 #define nlat 6 // Number of latitudes
#define nlev 5 // Number of levels
#define nts 3 // Number of time steps

10 int main(void)
{
    int gridID, zaxisID1, zaxisID2, taxisID;
    int vlistID, varID1, varID2, streamID, tsID;
    int i, nmiss = 0;
    double lons[nlon] = {0, 30, 60, 90, 120, 150, 180, 210, 240, 270, 300, 330};
    15 double lats[nlat] = {-75, -45, -15, 15, 45, 75};
    double levs[nlev] = {101300, 92500, 85000, 50000, 20000};
    double var1[nlon*nlat];
    double var2[nlon*nlat*nlev];

    20 // Create a regular lon/lat grid
    gridID = gridCreate(GRID_LONLAT, nlon*nlat);
    gridDefXsize(gridID, nlon);
    gridDefYsize(gridID, nlat);
    25 gridDefXvals(gridID, lons);
    gridDefYvals(gridID, lats);

    // Create a surface level Z-axis
    zaxisID1 = zaxisCreate(ZAXIS_SURFACE, 1);
    30 // Create a pressure level Z-axis
    zaxisID2 = zaxisCreate(ZAXIS_PRESSURE, nlev);
    zaxisDefLevels(zaxisID2, levs);

    // Create a variable list
    35 vlistID = vlistCreate();

    // Define the variables
    varID1 = vlistDefVar(vlistID, gridID, zaxisID1, TIME_VARIABLE);
    40 varID2 = vlistDefVar(vlistID, gridID, zaxisID2, TIME_VARIABLE);
```



```

// Define the variable names
vlistDefVarName(vlistID, varID1, "varname1");
vlistDefVarName(vlistID, varID2, "varname2");
45

// Create a Time axis
taxisID = taxisCreate(TAXIS_ABSOLUTE);

// Assign the Time axis to the variable list
50 vlistDefTaxis(vlistID, taxisID);

// Create a dataset in netCDF format
streamID = streamOpenWrite("example.nc", FILETYPE_NC);
if ( streamID < 0 )
55 {
    fprintf(stderr, "%s\n", cdiStringError(streamID));
    return(1);
}

// Assign the variable list to the dataset
60 streamDefVlist(streamID, vlistID);

// Loop over the number of time steps
for ( tsID = 0; tsID < nts; tsID++ )
65 {
    // Set the verification date to 1985-01-01 + tsID
    taxisDefVdate(taxisID, 19850101+tsID);
    // Set the verification time to 12:00:00
    taxisDefVtime(taxisID, 120000);
70 // Define the time step
    streamDefTimestep(streamID, tsID);

    // Init var1 and var2
    for ( i = 0; i < nlon*nlat; i++ ) var1[i] = 1.1;
75 for ( i = 0; i < nlon*nlat*nlev; i++ ) var2[i] = 2.2;

    // Write var1 and var2
    streamWriteVar(streamID, varID1, var1, nmiss);
    streamWriteVar(streamID, varID2, var2, nmiss);
80 }

// Close the output stream
streamClose(streamID);

// Destroy the objects
85 vlistDestroy(vlistID);
taxisDestroy(taxisID);
zaxisDestroy(zaxisID1);
zaxisDestroy(zaxisID2);
90 gridDestroy(gridID);

return 0;
}

```

B.1.1. Result

This is the `ncdump -h` output of the resulting netCDF file `example.nc`.

```

netcdf example {
2  dimensions:
    lon = 12 ;
    lat = 6 ;
    lev = 5 ;
    time = UNLIMITED ; // (3 currently)
7  variables :
    double lon(lon) ;
        lon:long_name = "longitude" ;
        lon:units = "degrees_east" ;
        lon:standard_name = "longitude" ;
12    double lat(lat) ;
        lat:long_name = "latitude" ;
        lat:units = "degrees_north" ;
        lat:standard_name = "latitude" ;
    double lev(lev) ;
17    lev:long_name = "pressure" ;
        lev:units = "Pa" ;
    double time(time) ;
        time:units = "day as %Y%m%d.%f" ;
    float varname1(time, lat, lon) ;
22    float varname2(time, lev, lat, lon) ;
data:

    lon = 0, 30, 60, 90, 120, 150, 180, 210, 240, 270, 300, 330 ;
27    lat = -75, -45, -15, 15, 45, 75 ;

    lev = 101300, 92500, 85000, 50000, 20000 ;

    time = 19850101.5, 19850102.5, 19850103.5 ;
32 }

```

B.2. Read a dataset

This example reads the netCDF file `example.nc` from [Appendix B.1](#).

```

#include <stdio.h>
#include "cdi.h"
3
int nlon = 12; // Number of longitudes
int nlat = 6; // Number of latitudes
int nlev = 5; // Number of levels
int nts = 3; // Number of time steps
8
int main(void)
{
    int taxisID, vlistID, varID1, varID2, streamID, tsID;
    int nmiss, vdate, vtime;
13    double var1[nlon*nlat];
    double var2[nlon*nlat*nlev];

    // Open the dataset
18    streamID = streamOpenRead("example.nc");
    if ( streamID < 0 )

```

```

    {
        fprintf(stderr, "%s\n", cdiStringError(streamID));
        return(1);
23    }

    // Get the variable list of the dataset
    vlistID = streamInqVlist(streamID);

28    // Set the variable IDs
    varID1 = 0;
    varID2 = 1;

    // Get the Time axis from the variable list
33    taxisID = vlistInqTaxis(vlistID);

    // Loop over the number of time steps
    for ( tsID = 0; tsID < nts; tsID++ )
    {
38        // Inquire the time step
        streamInqTimestep(streamID, tsID);

        // Get the verification date and time
43        vdate = taxisInqVdate(taxisID);
        vtime = taxisInqVtime(taxisID);

        // Read var1 and var2
        streamReadVar(streamID, varID1, var1, &nmiss);
        streamReadVar(streamID, varID2, var2, &nmiss);
48    }

    // Close the input stream
    streamClose(streamID);

53    return 0;
}

```

B.3. Copy a dataset

This example reads the netCDF file `example.nc` from [Appendix B.1](#) and writes the result to a GRIB dataset by simple setting the output file type to `FILETYPE_GRB`.

```

1  #include <stdio.h>
    #include "cdi.h"

    int nlon = 12; // Number of longitudes
    int nlat = 6;  // Number of latitudes
6   int nlev = 5;  // Number of levels
    int nts = 3;  // Number of time steps

    int main(void)
    {
11     int taxisID, vlistID1, vlistID2, varID1, varID2, streamID1, streamID2, tsID;
        int nmiss, vdate, vtime;
        double var1[nlon*nlat];
        double var2[nlon*nlat*nlev];

```

```

16 // Open the input dataset
streamID1 = streamOpenRead("example.nc");
if ( streamID1 < 0 )
{
21     fprintf(stderr, "%s\n", cdiStringError(streamID1));
    return(1);
}

// Get the variable list of the dataset
26 vlistID1 = streamInqVlist(streamID1);

// Set the variable IDs
varID1 = 0;
varID2 = 1;
31

// Get the Time axis from the variable list
taxisID = vlistInqTaxis(vlistID1);

// Open the output dataset (GRIB format)
36 streamID2 = streamOpenWrite("example.grb", FILETYPE_GRB);
if ( streamID2 < 0 )
{
    fprintf(stderr, "%s\n", cdiStringError(streamID2));
    return(1);
41 }

vlistID2 = vlistDuplicate(vlistID1);

streamDefVlist(streamID2, vlistID2);
46

// Loop over the number of time steps
for ( tsID = 0; tsID < nts; tsID++ )
{
    // Inquire the input time step
51     streamInqTimestep(streamID1, tsID);

    // Get the verification date and time
    vdate = taxisInqVdate(taxisID);
    vtime = taxisInqVtime(taxisID);
56

    // Define the output time step
    streamDefTimestep(streamID2, tsID);

    // Read var1 and var2
61     streamReadVar(streamID1, varID1, var1, &nmiss);
    streamReadVar(streamID1, varID2, var2, &nmiss);

    // Write var1 and var2
    streamWriteVar(streamID2, varID1, var1, nmiss);
66     streamWriteVar(streamID2, varID2, var2, nmiss);
}

// Close the streams
71 streamClose(streamID1);
streamClose(streamID2);

```

```
return 0;  
}
```

Function index

G

gridCreate	31
gridDefNP	33
gridDefXbounds	35
gridDefXlongname	36
gridDefXname	36
gridDefXsize	32
gridDefXunits	37
gridDefXvals	34
gridDefYbounds	35
gridDefYlongname	38
gridDefYname	37
gridDefYsize	33
gridDefYunits	38
gridDefYvals	34
gridDestroy	32
gridDuplicate	32
gridInqNP	34
gridInqSize	32
gridInqType	32
gridInqXbounds	35
gridInqXlongname	37
gridInqXname	36
gridInqXsize	33
gridInqXunits	37
gridInqXvals	34
gridInqYbounds	36
gridInqYlongname	38
gridInqYname	38
gridInqYsize	33
gridInqYunits	39
gridInqYvals	35

S

streamClose	15
streamDefByteorder	15
streamDefTimestep	16
streamDefVlist	16
streamInqByteorder	15
streamInqFiletype	15
streamInqTimestep	16
streamInqVlist	16
streamOpenRead	14

streamOpenWrite	13
streamReadVar	17
streamReadVarSlice	18
streamWriteVar	17
streamWriteVarF	17
streamWriteVarSlice	17
streamWriteVarSliceF	18

T

taxisCreate	45
taxisDefCalendar	47
taxisDefRdate	46
taxisDefRtime	46
taxisDefVdate	47
taxisDefVtime	47
taxisDestroy	46
taxisInqCalendar	48
taxisInqRdate	46
taxisInqRtime	46
taxisInqVdate	47
taxisInqVtime	47

V

vlistCat	20
vlistCopy	19
vlistCopyFlag	20
vlistCreate	19
vlistDefAttFlt	29
vlistDefAttInt	28
vlistDefAttTxt	30
vlistDefTaxis	21
vlistDefVar	22
vlistDefVarCode	23
vlistDefVarDatatype	26
vlistDefVarLongname	24
vlistDefVarMissval	26
vlistDefVarName	24
vlistDefVarStdname	25
vlistDefVarUnits	25
vlistDestroy	19
vlistDuplicate	19
vlistInqAtt	28
vlistInqAttFlt	29

vlistInqAttInt	29
vlistInqAttTxt	30
vlistInqNatts	28
vlistInqTaxis	21
vlistInqVarCode	23
vlistInqVarDatatype	26
vlistInqVarGrid	23
vlistInqVarLongname	24
vlistInqVarMissval	27
vlistInqVarName	24
vlistInqVarStdname	25
vlistInqVarUnits	25
vlistInqVarZaxis	23
vlistNgrids	20
vlistNvars	20
vlistNzaxis	20

Z

zaxisCreate	40
zaxisDefLevels	41
zaxisDefLongname	43
zaxisDefName	42
zaxisDefUnits	43
zaxisDestroy	41
zaxisInqLevel	42
zaxisInqLevels	42
zaxisInqLongname	43
zaxisInqName	42
zaxisInqSize	41
zaxisInqType	41
zaxisInqUnits	43